FlyCapture2 C 2.10.3.0

Generated by Doxygen 1.8.11

Contents

1	Dep	recated	List		1
2	Mod	lule Inde	ex		3
	2.1	Module	es		3
3	Data	Struct	ure Index		5
	3.1	Data S	tructures		5
4	File	Index			7
	4.1	File Lis	st		7
5	Mod	lule Doo	umentatio	on	9
	5.1	Bus M	anager Op	eration	9
		5.1.1	Detailed	Description	10
		5.1.2	Function	Documentation	10
			5.1.2.1	fc2DiscoverGigECameras(fc2Context context, fc2CameraInfo *gigECameras, unsigned int *arraySize)	10
			5.1.2.2	fc2FireBusReset(fc2Context context, fc2PGRGuid *pGuid)	11
			5.1.2.3	fc2ForceAllIPAddressesAutomatically()	11
			5.1.2.4	fc2ForceIPAddressAutomatically(unsigned int serialNumber)	11
			5.1.2.5	fc2ForceIPAddressToCamera(fc2Context context, fc2MACAddress macAddress, fc2IPAddress ipAddress, fc2IPAddress subnetMask, fc2IPAddress defaultGateway)	12
			5.1.2.6	fc2GetCameraFromIndex(fc2Context context, unsigned int index, fc2PGRGuid *pGuid)	12
			5.1.2.7	fc2GetCameraFromIPAddress(fc2Context context, fc2IPAddress ipAddress, fc2PGRGuid *pGuid)	12
			5.1.2.8	fc2GetCameraFromSerialNumber(fc2Context context, unsigned int serialNumber, fc2PGRGuid *pGuid)	13

iv CONTENTS

		5.1.2.9	fc2GetCameraSerialNumberFromIndex(fc2Context context, unsigned int index, unsigned int *pSerialNumber)	13
		5.1.2.10	fc2GetDeviceFromIndex(fc2Context context, unsigned int index, fc2PGRGuid *pGuid)	13
		5.1.2.11	fc2GetInterfaceTypeFromGuid(fc2Context context, fc2PGRGuid *pGuid, fc2↔ InterfaceType *pInterfaceType)	14
		5.1.2.12	fc2GetNumOfCameras(fc2Context context, unsigned int *pNumCameras)	14
		5.1.2.13	fc2GetNumOfDevices(fc2Context context, unsigned int *pNumDevices)	14
		5.1.2.14	fc2GetTopology(fc2Context context, fc2TopologyNodeContext *pTopology↔ NodeContext)	15
		5.1.2.15	fc2GetUsbLinkInfo(fc2Context context, fc2PGRGuid guid, unsigned int *pValue)	15
		5.1.2.16	fc2GetUsbPortStatus(fc2Context context, fc2PGRGuid guid, unsigned int *pValue)	15
		5.1.2.17	fc2lsCameraControlable(fc2Context context, fc2PGRGuid *pGuid, BOOL *p↔ Controlable)	16
		5.1.2.18	fc2ReadPhyRegister(fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int *pValue)	16
		5.1.2.19	$\label{lem:context} fc 2 Register Callback (fc 2 Context context, fc 2 Bus Event Callback enum Callback, fc 2 Bus Callback Type callback Type, void *pParameter, fc 2 Callback Handle *p Callback Handle)$	16
		5.1.2.20	fc2RescanBus(fc2Context context)	17
		5.1.2.21	fc2UnregisterCallback(fc2Context context, fc2CallbackHandle callbackHandle) .	17
		5.1.2.22	fc2WritePhyRegister(fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int value)	17
5.2	Conne	ction and I	Image Retrieval	19
	5.2.1	Detailed	Description	19
	5.2.2	Function	Documentation	19
		5.2.2.1	fc2Connect(fc2Context context, fc2PGRGuid *guid)	19
		5.2.2.2	fc2Disconnect(fc2Context context)	20
		5.2.2.3	fc2GetConfiguration(fc2Context context, fc2Config *config)	20
		5.2.2.4	fc2RetrieveBuffer(fc2Context context, fc2Image *pImage)	20
		5.2.2.5	fc2SetCallback(fc2Context context, fc2ImageEventCallback pCallbackFn, void *pCallbackData)	21
		5.2.2.6	fc2SetConfiguration(fc2Context context, fc2Config *config)	21
		5.2.2.7	fc2SetUserBuffers(fc2Context context, unsigned char *const ppMemBuffers, int size, int nNumBuffers)	22

CONTENTS

		5.2.2.8	fc2StartCapture(fc2Context context)	22
		5.2.2.9	fc2StartCaptureCallback(fc2Context context, fc2ImageEventCallback p← CallbackFn, void *pCallbackData)	23
		5.2.2.10	fc2StartSyncCapture(unsigned int numCameras, fc2Context *pContexts)	23
		5.2.2.11	fc2StartSyncCaptureCallback(unsigned int numCameras, fc2Context *pContexts, fc2ImageEventCallback *pCallbackFns, void **pCallbackDataArray)	23
		5.2.2.12	fc2StopCapture(fc2Context context)	24
		5.2.2.13	fc2WaitForBufferEvent(fc2Context context, fc2Image *pImage, unsigned int eventNumber)	24
5.3	Inform	ation and I	Properties	26
	5.3.1	Detailed	Description	26
	5.3.2	Function	Documentation	26
		5.3.2.1	fc2GetCameraInfo(fc2Context context, fc2CameraInfo *pCameraInfo)	26
		5.3.2.2	fc2GetProperty(fc2Context context, fc2Property *prop)	26
		5.3.2.3	fc2GetPropertyInfo(fc2Context context, fc2PropertyInfo *propInfo)	27
		5.3.2.4	fc2SetProperty(fc2Context context, fc2Property *prop)	27
		5.3.2.5	fc2SetPropertyBroadcast(fc2Context context, fc2Property *prop)	28
5.4	Genera	al Purpose	Input / Output	29
	5.4.1	Detailed	Description	29
	5.4.2	Function	Documentation	29
		5.4.2.1	fc2GetGPIOPinDirection(fc2Context context, unsigned int pin, unsigned int *p↔ Direction)	29
		5.4.2.2	fc2SetGPIOPinDirection(fc2Context context, unsigned int pin, unsigned int direction)	30
		5.4.2.3	fc2SetGPIOPinDirectionBroadcast(fc2Context context, unsigned int pin, unsigned int direction)	30
5.5	Trigger			31
	5.5.1	Detailed	Description	31
	5.5.2	Function	Documentation	31
		5.5.2.1	fc2FireSoftwareTrigger(fc2Context context)	31
		5.5.2.2	fc2FireSoftwareTriggerBroadcast(fc2Context context)	32
		5.5.2.3	fc2GetTriggerDelay(fc2Context context, fc2TriggerDelay *triggerDelay)	32
		5.5.2.4	fc2GetTriggerDelayInfo(fc2Context context, fc2TriggerDelayInfo *triggerDelayInfo)	32

vi

		5.5.2.5	fc2GetTriggerMode(fc2Context context, fc2TriggerMode *triggerMode)	33
		5.5.2.6	fc2GetTriggerModeInfo(fc2Context context, fc2TriggerModeInfo *triggerModeInfo)	33
		5.5.2.7	fc2SetTriggerDelay(fc2Context context, fc2TriggerDelay *triggerDelay)	34
		5.5.2.8	fc2SetTriggerDelayBroadcast(fc2Context context, fc2TriggerDelay *triggerDelay)	34
		5.5.2.9	fc2SetTriggerMode(fc2Context context, fc2TriggerMode *triggerMode)	35
		5.5.2.10	fc2SetTriggerModeBroadcast(fc2Context context, fc2TriggerMode *triggerMode)	35
5.6	Strobe			37
	5.6.1	Detailed	Description	37
	5.6.2	Function	Documentation	37
		5.6.2.1	fc2GetStrobe(fc2Context context, fc2StrobeControl *strobeControl)	37
		5.6.2.2	fc2GetStrobeInfo(fc2Context context, fc2StrobeInfo *strobeInfo)	37
		5.6.2.3	fc2SetStrobe(fc2Context context, fc2StrobeControl *strobeControl)	38
		5.6.2.4	fc2SetStrobeBroadcast(fc2Context context, fc2StrobeControl *strobeControl)	38
5.7	Look U	lp Table .		40
	5.7.1	Detailed	Description	40
	5.7.2	Function	Documentation	40
		5.7.2.1	fc2EnableLUT(fc2Context context, BOOL on)	40
		5.7.2.2	fc2GetActiveLUTBank(fc2Context context, unsigned int *pActiveBank)	41
		5.7.2.3	fc2GetLUTBankInfo(fc2Context context, unsigned int bank, BOOL *pRead← Supported, BOOL *pWriteSupported)	41
		5.7.2.4	fc2GetLUTChannel(fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int *pEntries)	41
		5.7.2.5	fc2GetLUTInfo(fc2Context context, fc2LUTData *pData)	42
		5.7.2.6	fc2SetActiveLUTBank(fc2Context context, unsigned int activeBank)	42
		5.7.2.7	fc2SetLUTChannel(fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int *pEntries)	43
5.8	Memor	ry Channe	ls	44
	5.8.1	Detailed	Description	44
	5.8.2	Function	Documentation	44
		5.8.2.1	fc2GetEmbeddedImageInfo(fc2Context context, fc2EmbeddedImageInfo *pInfo)	44
		5.8.2.2	fc2GetMemoryChannel(fc2Context context, unsigned int *pCurrentChannel)	45
		5.8.2.3	fc2GetMemoryChannelInfo(fc2Context context, unsigned int *pNumChannels) .	45

CONTENTS vii

		5.8.2.4	fc2RestoreFromMemoryChannel(fc2Context context, unsigned int channel)	45
		5.8.2.5	fc2SaveToMemoryChannel(fc2Context context, unsigned int channel)	46
		5.8.2.6	$fc2SetEmbeddedImageInfo(fc2Context\ context,\ fc2EmbeddedImageInfo\ *pInfo)\ .$	46
5.9	Registe	er Operatio	on	48
	5.9.1	Detailed	Description	48
	5.9.2	Function	Documentation	48
		5.9.2.1	fc2GetRegisterString(unsigned int registerVal)	48
		5.9.2.2	fc2ReadRegister(fc2Context context, unsigned int address, unsigned int *pValue)	48
		5.9.2.3	fc2ReadRegisterBlock(fc2Context context, unsigned short addressHigh, unsigned int addressLow, unsigned int *pBuffer, unsigned int length)	49
		5.9.2.4	fc2WriteRegister(fc2Context context, unsigned int address, unsigned int value) .	49
		5.9.2.5	fc2WriteRegisterBlock(fc2Context context, unsigned short addressHigh, unsigned int addressLow, const unsigned int *pBuffer, unsigned int length)	50
		5.9.2.6	fc2WriteRegisterBroadcast(fc2Context context, unsigned int address, unsigned int value)	50
5.10	DCAM	Formats		51
	5.10.1	Detailed	Description	51
	5.10.2	Function	Documentation	51
		5.10.2.1	fc2GetVideoModeAndFrameRate(fc2Context context, fc2VideoMode *video← Mode, fc2FrameRate *frameRate)	51
		5.10.2.2	fc2GetVideoModeAndFrameRateInfo(fc2Context context, fc2VideoMode video ← Mode, fc2FrameRate frameRate, BOOL *pSupported)	51
		5.10.2.3	fc2SetVideoModeAndFrameRate(fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate)	52
5.11	Format	7		53
	5.11.1	Detailed	Description	53
	5.11.2	Function	Documentation	53
		5.11.2.1	fc2GetFormat7Configuration(fc2Context context, fc2Format7ImageSettings *imageSettings, unsigned int *packetSize, float *percentage)	53
		5.11.2.2	fc2GetFormat7Info(fc2Context context, fc2Format7Info *info, BOOL *pSupported)	54
		5.11.2.3	fc2SetFormat7Configuration(fc2Context context, fc2Format7ImageSettings *imageSettings, float percentSpeed)	54
		5.11.2.4	fc2SetFormat7ConfigurationPacket(fc2Context context, fc2Format7Image ← Settings ∗imageSettings, unsigned int packetSize)	54

viii CONTENTS

		5.11.2.5	*imageSettings, BOOL *settingsAreValid, fc2Format7PacketInfo *packetInfo)	55
5.12	GVCP	Register C	Operation	56
	5.12.1	Detailed	Description	56
	5.12.2	Function	Documentation	56
		5.12.2.1	fc2ReadGVCPMemory(fc2Context context, unsigned int address, unsigned char *pBuffer, unsigned int length)	56
		5.12.2.2	fc2ReadGVCPRegister(fc2Context context, unsigned int address, unsigned int *pValue)	57
		5.12.2.3	fc2ReadGVCPRegisterBlock(fc2Context context, unsigned int address, unsigned int *pBuffer, unsigned int length)	57
		5.12.2.4	fc2WriteGVCPMemory(fc2Context context, unsigned int address, const unsigned char *pBuffer, unsigned int length)	57
		5.12.2.5	fc2WriteGVCPRegister(fc2Context context, unsigned int address, unsigned int value)	58
		5.12.2.6	fc2WriteGVCPRegisterBlock(fc2Context context, unsigned int address, const unsigned int *pBuffer, unsigned int length)	58
		5.12.2.7	fc2WriteGVCPRegisterBroadcast(fc2Context context, unsigned int address, unsigned int value)	58
E 10	o: =			
5.13	GigE p	roperty ma	anipulation	60
5.15			Description	60
5.15	5.13.1	Detailed		
5.15	5.13.1	Detailed Function	Description	60
5.13	5.13.1	Detailed Function 5.13.2.1	Description	60 60
5.13	5.13.1	Detailed Function 5.13.2.1 5.13.2.2	Description	60 60 60
	5.13.1 5.13.2	Detailed Function 5.13.2.1 5.13.2.2 5.13.2.3	Description	60 60 60
	5.13.1 5.13.2 GigE in	Function 5.13.2.1 5.13.2.2 5.13.2.3 mage setting	Description Documentation fc2DiscoverGigEPacketSize(fc2Context context, unsigned int *packetSize) fc2GetGigEProperty(fc2Context context, fc2GigEProperty *pGigEProp) fc2SetGigEProperty(fc2Context context, const fc2GigEProperty *pGigEProp)	60 60 60 61
	5.13.1 5.13.2 GigE in 5.14.1	Detailed Function 5.13.2.1 5.13.2.2 5.13.2.3 mage settin Detailed	Description Documentation fc2DiscoverGigEPacketSize(fc2Context context, unsigned int *packetSize) fc2GetGigEProperty(fc2Context context, fc2GigEProperty *pGigEProp) fc2SetGigEProperty(fc2Context context, const fc2GigEProperty *pGigEProp) ngs	60 60 60 61 62
	5.13.1 5.13.2 GigE in 5.14.1	Detailed Function 5.13.2.1 5.13.2.2 5.13.2.3 nage settin Detailed Function	Description Documentation fc2DiscoverGigEPacketSize(fc2Context context, unsigned int *packetSize) fc2GetGigEProperty(fc2Context context, fc2GigEProperty *pGigEProp) fc2SetGigEProperty(fc2Context context, const fc2GigEProperty *pGigEProp) ngs Description	600 600 600 611 622
	5.13.1 5.13.2 GigE in 5.14.1	Detailed Function 5.13.2.1 5.13.2.2 5.13.2.3 mage settin Detailed Function 5.14.2.1	Description Documentation fc2DiscoverGigEPacketSize(fc2Context context, unsigned int *packetSize) fc2GetGigEProperty(fc2Context context, fc2GigEProperty *pGigEProp) fc2SetGigEProperty(fc2Context context, const fc2GigEProperty *pGigEProp) ngs Description Documentation fc2GetGigEImageSettings(fc2Context context, fc2GigEImageSettings *pImage←	600 600 601 612 622 622
	5.13.1 5.13.2 GigE in 5.14.1	Detailed Function 5.13.2.1 5.13.2.2 5.13.2.3 nage settin Detailed Function 5.14.2.1	Description Documentation fc2DiscoverGigEPacketSize(fc2Context context, unsigned int *packetSize) fc2GetGigEProperty(fc2Context context, fc2GigEProperty *pGigEProp) fc2SetGigEProperty(fc2Context context, const fc2GigEProperty *pGigEProp) ngs Description Documentation fc2GetGigEImageSettings(fc2Context context, fc2GigEImageSettings *pImage ← Settings) fc2GetGigEImageSettingsInfo(fc2Context context, fc2GigEImageSettingsInfo	600 600 601 612 622 622

CONTENTS

		5.14.2.5	fc2SetGigEImageSettings(fc2Context context, const fc2GigEImageSettings *p lmageSettings)	63
		5.14.2.6	fc2SetGigEImagingMode(fc2Context context, fc2Mode mode)	64
5.15	GigE in	nage binni	ng settings	65
	5.15.1	Detailed	Description	65
	5.15.2	Function	Documentation	65
		5.15.2.1	fc2GetGigEImageBinningSettings(fc2Context context, unsigned int ∗horz⇔ BinnningValue, unsigned int ∗vertBinnningValue)	65
		5.15.2.2	fc2SetGigEImageBinningSettings(fc2Context context, unsigned int horz⇔ BinnningValue, unsigned int vertBinnningValue)	65
5.16	GigE in	nage strea	m configuration	67
	5.16.1	Detailed	Description	67
	5.16.2	Function	Documentation	67
		5.16.2.1	fc2GetGigEConfig(fc2Context context, fc2GigEConfig *pConfig)	67
		5.16.2.2	fc2GetGigEStreamChannelInfo(fc2Context context, unsigned int channel, fc2← GigEStreamChannel ∗pChannel)	67
		5.16.2.3	$fc2GetNumStreamChannels (fc2Context\ context,\ unsigned\ int\ *numChannels)\ .\ .$	68
		5.16.2.4	fc2SetGigEConfig(fc2Context context, const fc2GigEConfig *pConfig)	68
		5.16.2.5	fc2SetGigEStreamChannelInfo(fc2Context context, unsigned int channel, fc2← GigEStreamChannel *pChannel)	68
5.17	Image	Operation		70
	5.17.1	Detailed	Description	71
	5.17.2	Function	Documentation	71
		5.17.2.1	fc2CalculateImageStatistics(fc2Image *pImage, fc2ImageStatisticsContext *p ImageStatisticsContext)	71
		5.17.2.2	fc2ConvertImage(fc2Image *pImageIn, fc2Image *pImageOut)	71
		5.17.2.3	fc2ConvertImageTo(fc2PixelFormat format, fc2Image *pImageIn, fc2Image *p ImageOut)	71
		5.17.2.4	fc2CreateImage(fc2Image *pImage)	72
		5.17.2.5	fc2DestroyImage(fc2Image *image)	72
		5.17.2.6	fc2DetermineBitsPerPixel(fc2PixelFormat format, unsigned int *pBitsPerPixel)	72
		5.17.2.7	$fc2GetDefaultColorProcessing(fc2ColorProcessingAlgorithm *pDefaultMethod) \ .$	73
		5.17.2.8	fc2GetDefaultOutputFormat(fc2PixelFormat *pFormat)	73

CONTENTS

		5.17.2.9	fc2GetImageData(fc2Image *pImage, unsigned char **ppData)	73
		5.17.2.10	fc2GetImageTimeStamp(fc2Image *pImage)	74
		5.17.2.11	fc2SaveImage(fc2Image *pImage, const char *pFilename, fc2ImageFileFormat format)	74
		5.17.2.12	fc2SaveImageWithOption(fc2Image *pImage, const char *pFilename, fc2↔ ImageFileFormat format, void *pOption)	74
		5.17.2.13	$fc2 Set Default Color Processing (fc2 Color Processing Algorithm \ default Method) \ . \ . \ .$	75
		5.17.2.14	fc2SetDefaultOutputFormat(fc2PixelFormat format)	75
		5.17.2.15	fc2SetImageData(fc2Image *pImage, const unsigned char *pData, unsigned int dataSize)	75
		5.17.2.16	fc2SetImageDimensions(fc2Image *pImage, unsigned int rows, unsigned int cols, unsigned int stride, fc2PixelFormat pixelFormat, fc2BayerTileFormat bayerFormat)	76
5.18	Image	Statistics C	Operation	77
	5.18.1	Detailed [Description	78
	5.18.2	Function	Documentation	78
		5.18.2.1	$fc2 CreateImageStatistics(fc2 ImageStatisticsContext* *pImageStatisticsContext) \ .$	78
		5.18.2.2	$fc 2 Destroy Image Statistics (fc 2 Image Statistics Context\ image Statistics Context)\ .\ .$	78
		5.18.2.3	fc2GetChannelHistogram(fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, int **ppHistogram)	78
		5.18.2.4	fc2GetChannelMean(fc2ImageStatisticsContext imageStatisticsContext, fc2 \leftrightarrow StatisticsChannel channel, float *pPixelValueMean)	79
		5.18.2.5	$\label{lem:context} fc 2 Get Channel Num Pixel Values (fc 2 Image Statistics Context image Statistics Context, fc 2 Statistics Channel channel, unsigned int *pNum Pixel Values)$	79
		5.18.2.6	fc2GetChannelPixelValueRange(fc2ImageStatisticsContext imageStatistics Context, fc2StatisticsChannel channel, unsigned int *pPixelValueMin, unsigned int *pPixelValueMax)	79
		5.18.2.7	$fc2GetChannelRange(fc2ImageStatisticsContext\ imageStatisticsContext,\ fc2 {\leftarrow}\ StatisticsChannel\ channel\ ,\ unsigned\ int\ *pMin\ ,\ unsigned\ int\ *pMax)\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\ .\$	80
		5.18.2.8	fc2GetChannelStatus(fc2ImageStatisticsContext imageStatisticsContext, fc2↔ StatisticsChannel channel, BOOL *pEnabled)	80
		5.18.2.9	fc2GetImageStatistics(fc2ImageStatisticsContext imageStatisticsContext, fc2 \leftrightarrow StatisticsChannel channel, unsigned int *pRangeMin, unsigned int *pRangeMax, unsigned int *pPixelValueMin, unsigned int *pPixelValueMax, unsigned int *p \leftrightarrow NumPixelValues, float *pPixelValueMean, int **ppHistogram)	80
		5.18.2.10	$fc2ImageStatisticsDisableAll(fc2ImageStatisticsContext\ imageStatisticsContext)\ .$	81
		5.18.2.11	$fc2ImageStatisticsEnableAll(fc2ImageStatisticsContext\ imageStatisticsContext)\ \ .$	81

CONTENTS xi

		5.18.2.12	context)	81
		5.18.2.13	fc2ImageStatisticsEnableHSLOnly(fc2ImageStatisticsContext imageStatistics Context)	82
		5.18.2.14	fc2ImageStatisticsEnableRGBOnly(fc2ImageStatisticsContext imageStatistics↔ Context)	82
		5.18.2.15	fc2SetChannelStatus(fc2ImageStatisticsContext imageStatisticsContext, fc2- StatisticsChannel channel, BOOL enabled)	82
5.19	AVI Re	cording O	peration	84
	5.19.1	Detailed I	Description	84
	5.19.2	Function	Documentation	84
		5.19.2.1	fc2AVIAppend(fc2AVIContext AVIContext, fc2Image *pImage)	84
		5.19.2.2	fc2AVIClose(fc2AVIContext AVIContext)	84
		5.19.2.3	fc2AVIOpen(fc2AVIContext AVIContext, const char *pFileName, fc2AVIOption *pOption)	85
		5.19.2.4	fc2CreateAVI(fc2AVIContext *pAVIContext)	85
		5.19.2.5	fc2DestroyAVI(fc2AVIContext AVIContext)	85
		5.19.2.6	fc2H264Open(fc2AVIContext AVIContext, const char *pFileName, fc2H264 \leftarrow Option *pOption)	86
		5.19.2.7	fc2MJPGOpen(fc2AVIContext AVIContext, const char *pFileName, fc2MJPG↔ Option *pOption)	86
5.20	Topolog	gyNode Op	peration	87
	5.20.1	Detailed I	Description	88
	5.20.2	Function	Documentation	88
		5.20.2.1	fc2CreateTopologyNode(fc2TopologyNodeContext *pTopologyNodeContext) . .	88
		5.20.2.2	fc2DestroyTopologyNode(fc2TopologyNodeContext TopologyNodeContext)	88
		5.20.2.3	fc2TopologyNodeAddChild(fc2TopologyNodeContext TopologyNodeContext, fc2TopologyNodeContext TopologyNodeChildContext)	88
		5.20.2.4	fc2TopologyNodeAddPortType(fc2TopologyNodeContext TopologyNodeContext, fc2PortType portType)	89
		5.20.2.5	fc2TopologyNodeAssignGuidToNode(fc2TopologyNodeContext TopologyNode← Context, fc2PGRGuid guid, int deviceId)	89
		5.20.2.6	fc2TopologyNodeAssignGuidToNodeEx(fc2TopologyNodeContext Topology ← NodeContext, fc2PGRGuid guid, int deviceId, fc2NodeType nodeType)	89
		5.20.2.7	fc2TopologyNodeGetChild(fc2TopologyNodeContext TopologyNodeContext, unsigned int position, fc2TopologyNodeContext *pChildTopologyNodeContext)	90

xii CONTENTS

		5.20.2.8	$\label{localization} $	90
		5.20.2.9	fc2TopologyNodeGetGuid(fc2TopologyNodeContext TopologyNodeContext, fc2PGRGuid *pGuid)	90
		5.20.2.10	fc2TopologyNodeGetInterfaceType(fc2TopologyNodeContext TopologyNode ← Context, fc2InterfaceType *pInterfaceType)	91
		5.20.2.11	fc2TopologyNodeGetNodeType(fc2TopologyNodeContext TopologyNodeContext, fc2NodeType *pNodeType)	91
		5.20.2.12	fc2TopologyNodeGetNumChildren(fc2TopologyNodeContext TopologyNode ← Context, unsigned int *pNumChildNodes)	91
		5.20.2.13	fc2TopologyNodeGetNumPorts(fc2TopologyNodeContext TopologyNodeContext, unsigned int *pNumPorts)	91
		5.20.2.14	fc2TopologyNodeGetPortType(fc2TopologyNodeContext, unsigned int position, fc2PortType *pPortType)	92
5.21	Utilities			93
	5.21.1	Detailed I	Description	93
	5.21.2	Function	Documentation	93
		5.21.2.1	fc2CheckDriver(const fc2PGRGuid *pGuid)	93
		5.21.2.2	fc2ErrorToDescription(fc2Error error)	94
		5.21.2.3	fc2GetDriverDeviceName(const fc2PGRGuid *pGuid, char *pDeviceName, size_t *deviceNameLength)	94
		5.21.2.4	fc2GetLibraryVersion(fc2Version *pVersion)	94
		5.21.2.5	fc2GetSystemInfo(fc2SystemInfo *pSystemInfo)	95
		5.21.2.6	fc2LaunchBrowser(const char *pAddress)	96
		5.21.2.7	fc2LaunchCommand(const char *pCommand)	96
		5.21.2.8	fc2LaunchCommandAsync(const char *pCommand, fc2AsyncCommand← Callback pCallback, void *pUserData)	96
		5.21.2.9	fc2LaunchHelp(const char *pFileName)	97
5.22	TypeDe	efs		98
	5.22.1	Detailed I	Description	98
	5.22.2	Macro De	efinition Documentation	98
		5.22.2.1	FALSE	98
		5.22.2.2	FULL_32BIT_VALUE	98
		5.22.2.3	MAX_STRING_LENGTH	98

CONTENTS xiii

98	 									 							Ξ.	TRUI		2.2.4	5			
98	 									 						tion	enta	ocum	D	edef	Ţ	5.22.3		
98	 									 							L.	воо		2.3.1	5			
98	 									 					t.	ntex	/ICoı	fc2A\	<u>)</u>	2.3.2	5			
99	 									 						t.	ontex	fc2C	}	2.3.3	5			
99	 									 . .					t.	ntex	ıiCor	fc2G	ļ	2.3.4	5			
99	 									 						mpl	agel	fc2Im	5	2.3.5	5			
99	 									 		xt .	nte	sCoı	istic	Stati	ages	fc2Im	6	2.3.6	5			
99	 									 		t.	ıtex	Con	ode	gyN	polo	fc2Tc	,	2.3.7	5			
100	 									 										ons .	era	Enume	5.23	
105	 									 							ption	escri	d D	tailed	D	5.23.1		
105	 									 			on	ntatio	ımer	ocu	pe D	on Ty	ati	umera	Е	5.23.2		
105	 									 			on	catio	Allo	idth	ındw	fc2Ba		3.2.1	5			
105	 									 				ıat	orm:	ïleF	ıyerT	fc2Ba	<u>)</u>	3.2.2	5			
106	 									 				/pe	ckTy	llba	ısCa	fc2Bı	3	3.2.3	5			
106	 									 						eed	ısSp [,]	fc2Bı	ļ ·	3.2.4	5			
106	 									 	n.	rithr	lgoi	ngAl	essiı	roce	olorP	fc2C	;	3.2.5	5			
107	 									 					.	ӯрє	iverT	fc2Dı	6	3.2.6	5			
107	 									 							ror	fc2Er	,	3.2.7	5			
108	 									 					e .	Rate	amel	fc2Fr	3	3.2.8	5			
109	 									 					.	ode	abM	fc2Gi)	3.2.9	5			
109	 									 					out	med	abTi	fc2Gı	0	3.2.1	5			
109	 									 				nat	Form	- ilel	agel	fc2Im	1	3.2.1	5			
110	 									 					/pe	ceT\	erfac	fc2In	2	3.2.1	5			
															•	·				3.2.1				
111	 													d.	pee	usS	CleBi	fc2P(4	3.2.1	5			
															•					3.2.1				
																				3.2.1				
																				3.2.1				
																						GigE s	5.24	
			 -	 	•				•	 							2		. •••		~~	0	J 1	

xiv CONTENTS

		5.24.1	Detailed Description	4
		5.24.2	Enumeration Type Documentation	4
			5.24.2.1 fc2GigEPropertyType	4
	5.25	Structu	ires	5
		5.25.1	Detailed Description	6
	5.26	GigE s	pecific structures	17
		5.26.1	Detailed Description	17
	5.27	IIDC sp	pecific structures	8
		5.27.1	Detailed Description	8
	5.28	Image	saving structures	9
		5.28.1	Detailed Description	20
		5.28.2	Typedef Documentation	20
			5.28.2.1 fc2AsyncCommandCallback	20
			5.28.2.2 fc2BusEventCallback	20
			5.28.2.3 fc2CallbackHandle	20
			5.28.2.4 fc2CameraEventCallback	20
			5.28.2.5 fc2ImageEventCallback	20
		5.28.3	Enumeration Type Documentation	20
			5.28.3.1 fc2TIFFCompressionMethod	20
5	Data	Structu	ure Documentation 12	21
	6.1		Option Struct Reference	21
		6.1.1	Detailed Description	21
		6.1.2	Field Documentation	
			6.1.2.1 frameRate	21
			6.1.2.2 reserved	21
	6.2	fc2BMF	POption Struct Reference	22
		6.2.1	Detailed Description	22
		6.2.2	Field Documentation	
			6.2.2.1 indexedColor_8bit	
			6.2.2.2 reserved	

CONTENTS xv

6.3	fc2Car	neraInfo S	truct Reference	2
	6.3.1	Detailed	Description	:4
	6.3.2	Field Doo	cumentation	<u>'</u> 4
		6.3.2.1	applicationIPAddress	<u>'</u> 4
		6.3.2.2	applicationPort	<u>'</u> 4
		6.3.2.3	bayerTileFormat	<u>'</u> 4
		6.3.2.4	busNumber	<u>'</u> 4
		6.3.2.5	ccpStatus	<u>'</u> 4
		6.3.2.6	configROM	:5
		6.3.2.7	defaultGateway	:5
		6.3.2.8	driverName	:5
		6.3.2.9	driverType	:5
		6.3.2.10	firmwareBuildTime	:5
		6.3.2.11	firmwareVersion	:5
		6.3.2.12	gigEMajorVersion	:5
		6.3.2.13	gigEMinorVersion	:5
		6.3.2.14	iidcVer	:5
		6.3.2.15	interfaceType	:5
		6.3.2.16	ipAddress	:6
		6.3.2.17	isColorCamera	:6
		6.3.2.18	macAddress	:6
		6.3.2.19	maximumBusSpeed	:6
		6.3.2.20	modelName	:6
		6.3.2.21	nodeNumber	:6
		6.3.2.22	pcieBusSpeed	:6
		6.3.2.23	reserved	:6
		6.3.2.24	sensorInfo	:6
		6.3.2.25	sensorResolution	:6
		6.3.2.26	serialNumber	:7
		6.3.2.27	subnetMask	:7

xvi CONTENTS

		6.3.2.28	userDefinedName	7
		6.3.2.29	vendorName	7
		6.3.2.30	xmlURL1	7
		6.3.2.31	xmlURL2	7
6.4	fc2Car	meraStats	Struct Reference	7
	6.4.1	Detailed	Description	8
	6.4.2	Field Doo	cumentation	8
		6.4.2.1	cameraCurrents	8
		6.4.2.2	cameraPowerUp	8
		6.4.2.3	cameraVoltages	8
		6.4.2.4	imageCorrupt	8
		6.4.2.5	imageDriverDropped	8
		6.4.2.6	imageDropped	8
		6.4.2.7	imageXmitFailed	8
		6.4.2.8	numCurrents	8
		6.4.2.9	numResendPacketsReceived	Э
		6.4.2.10	numResendPacketsRequested	Э
		6.4.2.11	numVoltages	9
		6.4.2.12	portErrors	Э
		6.4.2.13	regReadFailed	9
		6.4.2.14	regWriteFailed	9
		6.4.2.15	reserved	9
		6.4.2.16	temperature	9
		6.4.2.17	timeSinceBusReset	9
		6.4.2.18	timeSinceInitialization	9
		6.4.2.19	timeStamp	9
6.5	fc2Cor	nfig Struct	Reference	9
	6.5.1	Detailed	Description	0
	6.5.2	Field Doo	cumentation	0
		6.5.2.1	asyncBusSpeed	0

CONTENTS xvii

		6.5.2.2	bandwidthAllocation	130
		6.5.2.3	grabMode	130
		6.5.2.4	grabTimeout	131
		6.5.2.5	highPerformanceRetrieveBuffer	131
		6.5.2.6	isochBusSpeed	131
		6.5.2.7	minNumImageNotifications	131
		6.5.2.8	numBuffers	131
		6.5.2.9	numImageNotifications	131
		6.5.2.10	registerTimeout	132
		6.5.2.11	registerTimeoutRetries	132
		6.5.2.12	reserved	132
6.6	fc2Cor	nfigROM S	truct Reference	132
	6.6.1	Detailed	Description	133
	6.6.2	Field Doo	cumentation	133
		6.6.2.1	chipldHi	133
		6.6.2.2	chipldLo	133
		6.6.2.3	nodeVendorld	133
		6.6.2.4	pszKeyword	133
		6.6.2.5	reserved	133
		6.6.2.6	unitSpecId	133
		6.6.2.7	unitSubSWVer	133
		6.6.2.8	unitSWVer	133
		6.6.2.9	vendorUniqueInfo_0	133
		6.6.2.10	vendorUniqueInfo_1	134
		6.6.2.11	vendorUniqueInfo_2	134
		6.6.2.12	vendorUniqueInfo_3	134
6.7	fc2Eml	oeddedIma	ageInfo Struct Reference	134
	6.7.1	Detailed	Description	134
	6.7.2	Field Doo	cumentation	135
		6.7.2.1	brightness	135

xviii CONTENTS

		6.7.2.2	exposure	 135
		6.7.2.3	frameCounter	 135
		6.7.2.4	gain	 135
		6.7.2.5	GPIOPinState	 135
		6.7.2.6	ROIPosition	 135
		6.7.2.7	shutter	 135
		6.7.2.8	strobePattern	 135
		6.7.2.9	timestamp	 135
		6.7.2.10	whiteBalance	 135
6.8	fc2Emb	oeddedIma	ageInfoProperty Struct Reference	 135
	6.8.1	Detailed	Description	 135
	6.8.2	Field Doo	cumentation	 136
		6.8.2.1	available	 136
		6.8.2.2	onOff	 136
6.9	fc2Eve	ntCallback	kData Struct Reference	 136
	6.9.1	Field Doo	cumentation	 136
		6.9.1.1	EventData	 136
		6.9.1.2	EventDataSize	 136
		6.9.1.3	EventID	 137
		6.9.1.4	EventName	 137
		6.9.1.5	EventTimestamp	 137
		6.9.1.6	EventUserData	 137
		6.9.1.7	EventUserDataSize	 137
6.10	fc2Eve	ntOptions	Struct Reference	 137
	6.10.1	Detailed	Description	 138
	6.10.2	Field Doo	cumentation	 138
		6.10.2.1	EventCallbackFcn	 138
		6.10.2.2	EventName	 138
		6.10.2.3	EventUserData	 138
		6.10.2.4	EventUserDataSize	 138

CONTENTS xix

6.11	fc2Forn	nat7ImageSettings Struct Reference
	6.11.1	Detailed Description
	6.11.2	Field Documentation
		6.11.2.1 height
		6.11.2.2 mode
		6.11.2.3 offsetX
		6.11.2.4 offsetY
		6.11.2.5 pixelFormat
		6.11.2.6 reserved
		6.11.2.7 width
6.12	fc2Forn	at7Info Struct Reference
	6.12.1	Detailed Description
	6.12.2	Field Documentation
		6.12.2.1 imageHStepSize
		6.12.2.2 imageVStepSize
		6.12.2.3 maxHeight
		6.12.2.4 maxPacketSize
		6.12.2.5 maxWidth
		6.12.2.6 minPacketSize
		6.12.2.7 mode
		6.12.2.8 offsetHStepSize
		6.12.2.9 offsetVStepSize
		6.12.2.10 packetSize
		6.12.2.11 percentage
		6.12.2.12 pixelFormatBitField
		6.12.2.13 reserved
		6.12.2.14 vendorPixelFormatBitField
6.13	fc2Forn	nat7PacketInfo Struct Reference
	6.13.1	Detailed Description
	6.13.2	Field Documentation

CONTENTS

		6.13.2.1	maxBytesPe	rPacket .			 	 	 	 	 	. 142
		6.13.2.2	recommende	edBytesPe	erPack	et	 	 	 	 	 	. 142
		6.13.2.3	reserved				 	 	 	 	 	. 143
		6.13.2.4	unitBytesPer	Packet			 	 	 	 	 	. 143
6.14	fc2GigI	EConfig St	truct Referenc	e			 	 	 	 	 	. 143
	6.14.1	Detailed	Description .				 	 	 	 	 	. 143
	6.14.2	Field Doo	cumentation .				 	 	 	 	 	. 143
		6.14.2.1	enablePacke	tResend			 	 	 	 	 	. 143
		6.14.2.2	registerTime	out			 	 	 	 	 	. 143
		6.14.2.3	registerTime	outRetrie	S		 	 	 	 	 	. 144
		6.14.2.4	reserved				 	 	 	 	 	. 144
6.15	fc2GigI	ElmageSe	ttings Struct R	leference			 	 	 	 	 	. 144
	6.15.1	Detailed	Description .				 	 	 	 	 	. 144
	6.15.2	Field Doo	cumentation .				 	 	 	 	 	. 144
		6.15.2.1	height				 	 	 	 	 	. 144
		6.15.2.2	offsetX				 	 	 	 	 	. 144
		6.15.2.3	offsetY				 	 	 	 	 	. 145
		6.15.2.4	pixelFormat				 	 	 	 	 	. 145
		6.15.2.5	reserved				 	 	 	 	 	. 145
		6.15.2.6	width				 	 	 	 	 	. 145
6.16	fc2GigI	ElmageSe	ttingsInfo Stru	ct Refere	nce .		 	 	 	 	 	. 145
	6.16.1	Detailed	Description .				 	 	 	 	 	. 146
	6.16.2	Field Doo	cumentation .				 	 	 	 	 	. 146
		6.16.2.1	imageHStep	Size			 	 	 	 	 	. 146
		6.16.2.2	imageVStep	Size			 	 	 	 	 	. 146
		6.16.2.3	maxHeight .				 	 	 	 	 	. 146
		6.16.2.4	maxWidth .				 	 	 	 	 	. 146
		6.16.2.5	offsetHStepS	Size			 	 	 	 	 	. 146
		6.16.2.6	offsetVStepS	Size			 	 	 	 	 	. 146
		6.16.2.7	pixelFormatE	BitField .			 	 	 	 	 	. 146

CONTENTS xxi

		6.16.2.8	reserved	 	146
		6.16.2.9	vendorPixelFormatBitField	 	147
6.17	fc2GigI	EProperty	Struct Reference	 	147
	6.17.1	Detailed	Description	 	147
	6.17.2	Field Doo	cumentation	 	147
		6.17.2.1	isReadable	 	147
		6.17.2.2	isWritable	 	147
		6.17.2.3	max	 	148
		6.17.2.4	min	 	148
		6.17.2.5	propType	 	148
		6.17.2.6	reserved	 	148
		6.17.2.7	value	 	148
6.18	fc2GigI	EStreamC	Channel Struct Reference	 	148
	6.18.1	Detailed	Description	 	149
	6.18.2	Field Doo	cumentation	 	149
		6.18.2.1	destinationlpAddress	 	149
		6.18.2.2	doNotFragment	 	149
		6.18.2.3	hostPort	 	149
		6.18.2.4	interPacketDelay	 	149
		6.18.2.5	networkInterfaceIndex	 	149
		6.18.2.6	packetSize	 	149
		6.18.2.7	reserved	 	149
		6.18.2.8	sourcePort	 	149
6.19	fc2H26	4Option S	Struct Reference	 	150
	6.19.1	Detailed	Description	 	150
	6.19.2	Field Doo	cumentation	 	150
		6.19.2.1	bitrate	 	150
		6.19.2.2	frameRate	 	150
		6.19.2.3	height	 	150
		6.19.2.4	reserved	 	150

xxii CONTENTS

		6.19.2.5	width	 	 	 	150
6.20	fc2Ima	ge Struct F	eference	 	 	 	151
	6.20.1	Field Doo	mentation	 	 	 	151
		6.20.1.1	bayerFormat	 	 	 	151
		6.20.1.2	cols	 	 	 	151
		6.20.1.3	dataSize	 	 	 	151
		6.20.1.4	format	 	 	 	151
		6.20.1.5	imageImpl	 	 	 	151
		6.20.1.6	pData	 	 	 	151
		6.20.1.7	receivedDataSize	 	 	 	151
		6.20.1.8	rows	 	 	 	151
		6.20.1.9	stride	 	 	 	151
6.21	fc2lma	geMetadat	Struct Reference	 	 	 	151
	6.21.1	Detailed	escription	 	 	 	152
	6.21.2	Field Doo	mentation	 	 	 	152
		6.21.2.1	embeddedBrightness	 	 	 	152
		6.21.2.2	embeddedExposure	 	 	 	152
		6.21.2.3	embeddedFrameCounter	 	 	 	152
		6.21.2.4	embeddedGain	 	 	 	152
		6.21.2.5	embeddedGPIOPinState	 	 	 	153
		6.21.2.6	embeddedROIPosition	 	 	 	153
		6.21.2.7	embeddedShutter	 	 	 	153
		6.21.2.8	embeddedStrobePattern	 	 	 	153
		6.21.2.9	embeddedTimeStamp	 	 	 	153
		6.21.2.10	embeddedWhiteBalance	 	 	 	153
		6.21.2.11	reserved	 	 	 	153
6.22	fc2Inter	rnalConte	Struct Reference	 	 	 	153
	6.22.1	Field Doo	mentation	 	 	 	154
		6.22.1.1	pBusMgr	 	 	 	154
		6.22.1.2	pCamera	 	 	 	154

CONTENTS xxiii

6.23 fc2InternalGuiContext Struct Reference	54
6.23.1 Field Documentation	54
6.23.1.1 pCameraControlDlg	54
6.23.1.2 pCameraSelectionDlg	54
6.24 fc2InternalImageCallback Struct Reference	54
6.24.1 Field Documentation	54
6.24.1.1 pCallback	54
6.24.1.2 pCallbackData	54
6.25 fc2IPAddress Struct Reference	55
6.25.1 Detailed Description	55
6.25.2 Field Documentation	55
6.25.2.1 octets	55
6.26 fc2JPEGOption Struct Reference	55
6.26.1 Detailed Description	55
6.26.2 Field Documentation	55
6.26.2.1 progressive	55
6.26.2.2 quality	56
6.26.2.3 reserved	56
6.27 fc2JPG2Option Struct Reference	56
6.27.1 Detailed Description	56
6.27.2 Field Documentation	56
6.27.2.1 quality	56
6.27.2.2 reserved	57
6.28 fc2LUTData Struct Reference	57
6.28.1 Detailed Description	57
6.28.2 Field Documentation	57
6.28.2.1 enabled	57
6.28.2.2 inputBitDepth	57
6.28.2.3 numBanks	58
6.28.2.4 numChannels	58

xxiv CONTENTS

	6.28.2.5 numEntries	58
	6.28.2.6 outputBitDepth	58
	6.28.2.7 reserved	58
	6.28.2.8 supported	58
6.29 fc2MA	ACAddress Struct Reference	58
6.29.1	Detailed Description	58
6.29.2	Prield Documentation	59
	6.29.2.1 octets	59
6.30 fc2MJ	PGOption Struct Reference	59
6.30.1	Detailed Description	59
6.30.2	Prield Documentation	59
	6.30.2.1 frameRate	59
	6.30.2.2 quality	59
	6.30.2.3 reserved	59
6.31 fc2PG	MOption Struct Reference	30
6.31.1	Detailed Description	30
6.31.2	Prield Documentation	30
	6.31.2.1 binaryFile	30
	6.31.2.2 reserved	60
6.32 fc2PG	RGuid Struct Reference	60
6.32.1	Detailed Description	30
6.32.2	Prield Documentation	31
	6.32.2.1 value	31
6.33 fc2PN	GOption Struct Reference	31
6.33.1	Detailed Description	31
6.33.2	Prield Documentation	31
	6.33.2.1 compressionLevel	31
	6.33.2.2 interlaced	31
	6.33.2.3 reserved	31
6.34 fc2PP	MOption Struct Reference	32

CONTENTS xxv

	6.34.1	Detailed Description	32
	6.34.2	Field Documentation	62
		6.34.2.1 binaryFile	32
		6.34.2.2 reserved	62
6.35	fc2Stro	bbeControl Struct Reference	32
	6.35.1	Detailed Description	33
	6.35.2	Field Documentation	33
		6.35.2.1 delay	33
		6.35.2.2 duration	63
		6.35.2.3 onOff	63
		6.35.2.4 polarity	63
		6.35.2.5 reserved	63
		6.35.2.6 source	63
6.36	fc2Stro	obelnfo Struct Reference	63
		Detailed Description	
		Field Documentation	
	0.00.2	6.36.2.1 maxValue	
		6.36.2.2 minValue	
		6.36.2.3 onOffSupported	
		6.36.2.4 polaritySupported	
		6.36.2.5 present	
		6.36.2.6 readOutSupported	
		6.36.2.7 reserved	
		6.36.2.8 source	
6.37	•	temInfo Struct Reference	
	6.37.1	Detailed Description	36
	6.37.2	Field Documentation	36
		6.37.2.1 byteOrder	
		6.37.2.2 cpuDescription	36
		6.37.2.3 driverList	36

xxvi CONTENTS

| | | 6.37.2.4 | gpuDescri | ption | |
 | 166 |
|---------|---------|------------|---------------|-------|---|------|------|------|------|------|------|------|------|-----|
| | | 6.37.2.5 | libraryList | | |
 | 166 |
| | | 6.37.2.6 | numCpuC | ores | |
 | 166 |
| | | 6.37.2.7 | osDescript | tion | |
 | 166 |
| | | 6.37.2.8 | osType . | | |
 | 166 |
| | | 6.37.2.9 | reserved | | |
 | 166 |
| | | 6.37.2.10 |) screenHei | ght . | |
 | 167 |
| | | 6.37.2.11 | screenWid | lth . | |
 | 167 |
| | | 6.37.2.12 | 2 sysMemSi | ze . | |
 | 167 |
| 6.38 fc | c2TIFF | Option St | ruct Referei | nce | |
 | 167 |
| 6 | 5.38.1 | Detailed | Description | | |
 | 167 |
| 6 | 5.38.2 | Field Doo | cumentation | | |
 | 167 |
| | | 6.38.2.1 | compressi | on . | |
 | 167 |
| | | 6.38.2.2 | reserved | | |
 | 167 |
| 6.39 fc | c2Time | Stamp St | truct Refere | nce | |
 | 168 |
| 6 | 8.39.1 | Detailed | Description | | |
 | 168 |
| 6 | 5.39.2 | Field Doo | cumentation | | |
 | 168 |
| | | 6.39.2.1 | cycleCoun | t | |
 | 168 |
| | | 6.39.2.2 | cycleOffse | t | |
 | 168 |
| | | 6.39.2.3 | cycleSeco | nds | |
 | 168 |
| | | 6.39.2.4 | microSeco | nds | |
 | 168 |
| | | 6.39.2.5 | reserved | | |
 | 168 |
| | | 6.39.2.6 | seconds | | |
 | 169 |
| 6.40 fc | c2Trigg | gerDelay S | Struct Refere | ence | |
 | 169 |
| 6 | 6.40.1 | Detailed | Description | | |
 | 169 |
| 6 | 6.40.2 | Field Doo | cumentation | | |
 | 170 |
| | | 6.40.2.1 | absContro | ١ | |
 | 170 |
| | | 6.40.2.2 | absValue | | |
 | 170 |
| | | 6.40.2.3 | autoManua | alMod | e |
 | 170 |
| | | 6.40.2.4 | onePush | | |
 | 170 |

CONTENTS xxvii

	6.40.2.5 onOff	
	6.40.2.6 present	
	6.40.2.7 reserved	
	6.40.2.8 type	
	6.40.2.9 valueA	
	6.40.2.10 valueB	
6.41 fc2	ggerDelayInfo Struct Reference	
6.4	Detailed Description	
6.4	2 Field Documentation	
	6.41.2.1 absMax	
	6.41.2.2 absMin	
	6.41.2.3 absValSupported	
	6.41.2.4 autoSupported	
	6.41.2.5 manualSupported	
	6.41.2.6 max	
	6.41.2.7 min	
	6.41.2.8 onePushSupported	
	6.41.2.9 onOffSupported	
	6.41.2.10 present	
	6.41.2.11 pUnitAbbr	
	6.41.2.12 pUnits	
	6.41.2.13 readOutSupported	
	6.41.2.14 reserved	
	6.41.2.15 type	
6.42 fc2	ggerMode Struct Reference	
6.4	Detailed Description	
6.4	2 Field Documentation	
	6.42.2.1 mode	
	6.42.2.2 onOff	
	6.42.2.3 parameter	

xxviii CONTENTS

	6.42.2.4	polarity .				 	 	 	 	 	 174
	6.42.2.5	reserved				 	 	 	 	 	 174
	6.42.2.6	source .				 	 	 	 	 	 175
6.43 fc2Trig	ıgerModelr	nfo Struct Re	eference			 	 	 	 	 	 175
6.43.1	Detailed	Description				 	 	 	 	 	 175
6.43.2	Field Doo	cumentation				 	 	 	 	 	 175
	6.43.2.1	modeMas	<			 	 	 	 	 	 175
	6.43.2.2	onOffSupp	oorted .			 	 	 	 	 	 176
	6.43.2.3	polaritySu	pported			 	 	 	 	 	 176
	6.43.2.4	present .				 	 	 	 	 	 176
	6.43.2.5	readOutSu	upported	١		 	 	 	 	 	 176
	6.43.2.6	reserved				 	 	 	 	 	 176
	6.43.2.7	softwareTr	iggerSu	pported	d	 	 	 	 	 	 176
	6.43.2.8	sourceMa	sk			 	 	 	 	 	 176
	6.43.2.9	valueRead	lable			 	 	 	 	 	 176
6.44 fc2Ver	sion Struct	Reference				 	 	 	 	 	 176
6.44.1	Detailed	Description				 	 	 	 	 	 177
6.44.2	Field Doo	cumentation				 	 	 	 	 	 177
	6.44.2.1	build				 	 	 	 	 	 177
	6.44.2.2	major				 	 	 	 	 	 177
	6.44.2.3	minor				 	 	 	 	 	 177
	6.44.2.4	type				 	 	 	 	 	 177

CONTENTS xxix

7	File	Docum	entation		179
	7.1	FlyCap	oture2_C.h	File Reference	179
	7.2	FlyCap	oture2Defs	_C.h File Reference	179
		7.2.1	Enumera	tion Type Documentation	188
			7.2.1.1	fc2ByteOrder	188
			7.2.1.2	fc2NodeType	188
			7.2.1.3	fc2OSType	188
			7.2.1.4	fc2PortType	189
			7.2.1.5	fc2StatisticsChannel	189
	7.3	FlyCap	oture2GUI_	_C.h File Reference	189
		7.3.1	Function	Documentation	190
			7.3.1.1	fc2CreateGUIContext(fc2GuiContext *pContext)	190
			7.3.1.2	fc2DestroyGUIContext(fc2GuiContext context)	190
			7.3.1.3	fc2Disonnect(fc2GuiContext context)attribute((deprecated))	190
			7.3.1.4	fc2GUIConnect(fc2GuiContext context, fc2Context cameraContext)	190
			7.3.1.5	fc2GUIDisconnect(fc2GuiContext context)	191
			7.3.1.6	fc2Hide(fc2GuiContext context)	191
			7.3.1.7	fc2IsVisible(fc2GuiContext context)	191
			7.3.1.8	fc2Show(fc2GuiContext context)	192
			7.3.1.9	fc2ShowModal(fc2GuiContext context, BOOL *pOkSelected, fc2PGRGuid *guidArray, unsigned int *size)	192
	7.4	FlyCap	oture2Inter	nal_C.h File Reference	192
		7.4.1	Function	Documentation	193
			7.4.1.1	IsContextValid(fc2Context context)	193
			7.4.1.2	IsGuiContextValid(fc2GuiContext context)	193
			7.4.1.3	SyncCppImageToStruct(fc2Image *pImage)	193
	7.5	FlyCap	oture2Platf	orm_C.h File Reference	193
		7.5.1	Macro De	efinition Documentation	193
			7.5.1.1	FLYCAPTURE2_C_API	193
			7.5.1.2	FLYCAPTURE2_C_CALL_CONVEN	193
	7.6	FlyCap	oture2Priva	ate_C.h File Reference	193

CONTENTS

	7.6.1	Function	Documentation	193
		7.6.1.1	GetInternal(unsigned int index)	193
7.7	MultiSy	yncLibrary ₋	_C.h File Reference	193
	7.7.1	Function	Documentation	194
		7.7.1.1	syncCreateContext(syncContext *pContext)	194
		7.7.1.2	syncDestroyContext(syncContext context)	194
		7.7.1.3	syncDisableCrossPCSynchronization(syncContext context)	195
		7.7.1.4	syncEnableCrossPCSynchronization(syncContext context)	195
		7.7.1.5	syncGetStatus(syncContext context)	195
		7.7.1.6	syncGetTimeSinceSynced(syncContext context)	196
		7.7.1.7	synclsTimingBusConnected(syncContext context)	196
		7.7.1.8	syncQueryCrossPCSynchronizationSetting(syncContext context)	196
		7.7.1.9	syncRescanMasterTimingBus(syncContext context)	196
		7.7.1.10	syncStart(syncContext context)	197
		7.7.1.11	syncStop(syncContext context)	197
7.8	MultiSy	yncLibraryl	Defs_C.h File Reference	197
	7.8.1	Macro De	efinition Documentation	198
		7.8.1.1	FALSE	198
		7.8.1.2	FULL_32BIT_VALUE	198
		7.8.1.3	MAX_STRING_LENGTH	198
		7.8.1.4	TRUE	198
	7.8.2	Typedef [Documentation	198
		7.8.2.1	BOOL	198
		7.8.2.2	syncContext	198
	7.8.3	Enumera	tion Type Documentation	198
		7.8.3.1	syncError	198
		7.8.3.2	syncMessage	199
7.9	MultiSy	yncLibraryl	Platform_C.h File Reference	199
	7.9.1	Macro De	efinition Documentation	199
		7.9.1.1	MULTISYNCLIBRARY_C_API	199
		7.9.1.2	MULTISYNCLIBRARY_C_CALL_CONVEN	199
Index				201

Chapter 1

Deprecated List

Global fc2Disonnect (fc2GuiContext context) __attribute__((deprecated))

This method is deprecated and will be removed in a future FlyCapture2 release. Please use fc2GUIDisconnect instead.

2 Deprecated List

Chapter 2

Module Index

2.1 Modules

Here is a list of all modules:

4 Module Index

Chapter 3

Data Structure Index

3.1 Data Structures

Here are the data structures with brief descriptions:

fc2AVIOption
Options for saving AVI files
fc2BMPOption
Options for saving Bitmap image
fc2CameraInfo
Camera information
fc2CameraStats
Camera diagnostic information
fc2Config
Configuration for a camera
fc2ConfigROM
Camera configuration ROM
fc2EmbeddedImageInfo
Properties of the possible embedded image information
fc2EmbeddedImageInfoProperty
Properties of a single embedded image info property
fc2EventCallbackData
fc2EventOptions
Options for enabling device event registration
fc2Format7ImageSettings
Format 7 image settings
fc2Format7Info
Format 7 information for a single mode
fc2Format7PacketInfo
Format 7 packet information
fc2GigEConfig
Configuration for a GigE camera
fc2GigEImageSettings
Image settings for a GigE camera
fc2GigEImageSettingsInfo
Format 7 information for a single mode
fc2GigEProperty
A GigE property
fc2GigEStreamChannel
Information about a single GigE stream channel

6 Data Structure Index

fc2H264Option	
Options for saving H264 files	150
	151
fc2ImageMetadata	
	151
	153
	154
	154
fc2IPAddress IPv4 address	155
IPv4 address	155
	155
fc2JPG2Option	133
	156
fc2LUTData	
	157
fc2MACAddress	
MAC address	158
fc2MJPGOption	
Options for saving MJPG files	159
fc2PGMOption	
Options for saving PGM images	160
fc2PGRGuid	
	160
fc2PNGOption	
Options for saving PNG images	161
fc2PPMOption	400
- 1	162
fc2StrobeControl	162
A camera strobe	102
	163
fc2SystemInfo	
•	165
fc2TIFFOption	
	167
fc2TimeStamp	
Timestamp information	168
fc2TriggerDelay	
' ' ' '	169
fc2TriggerDelayInfo	
	171
fc2TriggerMode	
A camera trigger	173
fc2TriggerModeInfo	475
Information about a camera trigger property	1/5
fc2Version The current version of the library	170
The current version of the library	176

Chapter 4

File Index

4.1 File List

Here is a list of all files with brief descriptions:

lyCapture2_C.h
lyCapture2Defs_C.h
lyCapture2GUI_C.h
lyCapture2Internal_C.h 192
lyCapture2Platform_C.h
lyCapture2Private_C.h
IultiSyncLibrary_C.h
IultiSyncLibraryDefs_C.h
lultiSyncLibraryPlatform_C.h

8 File Index

Chapter 5

Module Documentation

5.1 Bus Manager Operation

The functions in this section provide access to BusManager operations.

Functions

- FLYCAPTURE2_C_API fc2Error fc2FireBusReset (fc2Context context, fc2PGRGuid *pGuid)
 Fire a bus reset.
- FLYCAPTURE2_C_API fc2Error fc2GetNumOfCameras (fc2Context context, unsigned int *pNumCameras)

 Gets the number of cameras attached to the PC.
- FLYCAPTURE2_C_API fc2Error fc2GetCameraFromIPAddress (fc2Context context, fc2IPAddress ip
 — Address, fc2PGRGuid *pGuid)

Gets the PGRGuid for a camera with the specified IPv4 address.

FLYCAPTURE2_C_API fc2Error fc2GetCameraFromIndex (fc2Context context, unsigned int index, fc2PG
 — RGuid *pGuid)

Gets the PGRGuid for a camera on the PC.

FLYCAPTURE2_C_API fc2Error fc2GetCameraFromSerialNumber (fc2Context context, unsigned int serial
 — Number, fc2PGRGuid *pGuid)

Gets the PGRGuid for a camera on the PC.

 FLYCAPTURE2_C_API fc2Error fc2GetCameraSerialNumberFromIndex (fc2Context context, unsigned int index, unsigned int *pSerialNumber)

Gets the serial number of the camera with the specified index.

FLYCAPTURE2_C_API fc2Error fc2GetInterfaceTypeFromGuid (fc2Context context, fc2PGRGuid *pGuid, fc2InterfaceType *pInterfaceType)

Gets the interface type associated with a PGRGuid.

- FLYCAPTURE2_C_API fc2Error fc2GetNumOfDevices (fc2Context context, unsigned int *pNumDevices)

 Gets the number of devices.
- FLYCAPTURE2_C_API fc2Error fc2GetDeviceFromIndex (fc2Context context, unsigned int index, fc2PGR← Guid *pGuid)

Gets the PGRGuid for a device.

• FLYCAPTURE2_C_API fc2Error fc2ReadPhyRegister (fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int *pValue)

Read a phy register on the specified device.

• FLYCAPTURE2_C_API fc2Error fc2WritePhyRegister (fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int value)

Write a phy register on the specified device.

 FLYCAPTURE2_C_API fc2Error fc2GetUsbLinkInfo (fc2Context context, fc2PGRGuid guid, unsigned int *pValue)

Read usb link info for the port that the specified device is connected to.

 FLYCAPTURE2_C_API fc2Error fc2GetUsbPortStatus (fc2Context context, fc2PGRGuid guid, unsigned int *pValue)

Read usb port status for the port that the specified device is connected to.

FLYCAPTURE2_C_API fc2Error fc2GetTopology (fc2Context context, fc2TopologyNodeContext *p
 — TopologyNodeContext)

Gets the topology information for the PC.

• FLYCAPTURE2_C_API fc2Error fc2RegisterCallback (fc2Context context, fc2BusEventCallback enum ← Callback, fc2BusCallbackType callbackType, void *pParameter, fc2CallbackHandle *pCallbackHandle)

Register a callback function that will be called when the specified callback event occurs.

FLYCAPTURE2_C_API fc2Error fc2UnregisterCallback (fc2Context context, fc2CallbackHandle callback
 Handle)

Unregister a callback function.

• FLYCAPTURE2_C_API fc2Error fc2RescanBus (fc2Context context)

Force a rescan of the buses.

FLYCAPTURE2_C_API fc2Error fc2ForceIPAddressToCamera (fc2Context context, fc2MACAddress mac
 — Address, fc2IPAddress ipAddress, fc2IPAddress subnetMask, fc2IPAddress defaultGateway)

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

• FLYCAPTURE2 C API fc2Error fc2ForceAllIPAddressesAutomatically ()

Force all cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that they are connected to.

FLYCAPTURE2_C_API fc2Error fc2ForceIPAddressAutomatically (unsigned int serialNumber)

Force cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that it is connected to.

• FLYCAPTURE2_C_API fc2Error fc2DiscoverGigECameras (fc2Context context, fc2CameraInfo *gigE← Cameras, unsigned int *arraySize)

Discover all cameras connected to the network even if they reside on a different subnet.

FLYCAPTURE2_C_API fc2Error fc2lsCameraControlable (fc2Context context, fc2PGRGuid *pGuid, BOOL *pControlable)

Query whether a GigE camera is controllable.

5.1.1 Detailed Description

The functions in this section provide access to BusManager operations.

5.1.2 Function Documentation

5.1.2.1 FLYCAPTURE2_C_API fc2Error fc2DiscoverGigECameras (fc2Context *context*, fc2CameraInfo * *gigECameras*, unsigned int * *arraySize*)

Discover all cameras connected to the network even if they reside on a different subnet.

This is useful in situations where a GigE camera is using Persistent IP and the application's subnet is different from the device subnet. After discovering the camera, it is easy to use ForceIPAddressToCamera() to set a different IP configuration.

Parameters

context	The fc2Context to be used.	
gigECameras	Pointer to an array of CameraInfo structures.	
arraySize	Size of the array. Number of discovered cameras is returned in the same value.	

Returns

An Error indicating the success or failure of the function. If the error is PGRERROR_BUFFER_TOO_SMALL then arraySize will contain the minimum size needed for gigECameras array.

5.1.2.2 FLYCAPTURE2_C_API fc2Error fc2FireBusReset (fc2Context context, fc2PGRGuid * pGuid)

Fire a bus reset.

The actual bus reset is only fired for the specified 1394 bus, but it will effectively cause a global bus reset for the library.

Parameters

context	The fc2Context to be used.
pGuid	PGRGuid of the camera or the device to cause bus reset.

Returns

An Error indicating the success or failure of the function.

5.1.2.3 FLYCAPTURE2_C_API fc2Error fc2ForceAllIPAddressesAutomatically ()

Force all cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that they are connected to.

This is useful in situations where a GigE Vision cameras are using Persistent IP addresses and the application's subnet is different from the devices.

Returns

An Error indicating the success or failure of the function.

5.1.2.4 FLYCAPTURE2_C_API fc2Error fc2ForcelPAddressAutomatically (unsigned int serialNumber)

Force cameras on the network to be assigned sequential IP addresses on the same subnet as the network adapters that it is connected to.

This is useful in situations where a GigE Vision cameras is using Persistent IP addresses and the application's subnet is different from the device.

Returns

5.1.2.5 FLYCAPTURE2_C_API fc2Error fc2ForcelPAddressToCamera (fc2Context context, fc2MACAddress macAddress, fc2IPAddress ipAddress, fc2IPAddress subnetMask, fc2IPAddress defaultGateway)

Force the camera with the specific MAC address to the specified IP address, subnet mask and default gateway.

This is useful in situations where a GigE Vision camera is using Persistent IP and the application's subnet is different from the device subnet.

Parameters

context	The fc2Context to be used.
macAddress	MAC address of the camera.
ipAddress	IP address to set on the camera.
subnetMask	Subnet mask to set on the camera.
defaultGateway	Default gateway to set on the camera.

Returns

An Error indicating the success or failure of the function.

5.1.2.6 FLYCAPTURE2_C_API fc2Error fc2GetCameraFromIndex (fc2Context context, unsigned int index, fc2PGRGuid * pGuid)

Gets the PGRGuid for a camera on the PC.

It uniquely identifies the camera specified by the index and is used to identify the camera during a fc2Connect() call.

Parameters

context	The fc2Context to be used.
index	Zero based index of camera.
pGuid	Unique PGRGuid for the camera.

Returns

A fc2Error indicating the success or failure of the function.

5.1.2.7 FLYCAPTURE2_C_API fc2Error fc2GetCameraFromIPAddress (fc2Context context, fc2IPAddress ipAddress, fc2PGRGuid * pGuid)

Gets the PGRGuid for a camera with the specified IPv4 address.

context	The fc2Context to be used.
ipAddress	IP address to get GUID for.
pGuid	Unique PGRGuid for the camera.

Returns

A fc2Error indicating the success or failure of the function.

5.1.2.8 FLYCAPTURE2_C_API fc2Error fc2GetCameraFromSerialNumber (fc2Context context, unsigned int serialNumber, fc2PGRGuid * pGuid)

Gets the PGRGuid for a camera on the PC.

It uniquely identifies the camera specified by the serial number and is used to identify the camera during a fc2 Connect() call.

Parameters

context	The fc2Context to be used.
serialNumber	Serial number of camera.
pGuid	Unique PGRGuid for the camera.

Returns

A fc2Error indicating the success or failure of the function.

5.1.2.9 FLYCAPTURE2_C_API fc2Error fc2GetCameraSerialNumberFromIndex (fc2Context context, unsigned int index, unsigned int * pSerialNumber)

Gets the serial number of the camera with the specified index.

Parameters

context	The fc2Context to be used.
index	Zero based index of desired camera.
pSerialNumber	Serial number of camera.

Returns

A fc2Error indicating the success or failure of the function.

5.1.2.10 FLYCAPTURE2_C_API fc2Error fc2GetDeviceFromIndex (fc2Context context, unsigned int index, fc2PGRGuid * pGuid)

Gets the PGRGuid for a device.

It uniquely identifies the device specified by the index.

Parameters

context	The fc2Context to be used.
index	Zero based index of device.
pGuid	Unique PGRGuid for the device.

Generated by Doxygen

See also

fc2GetNumOfDevices()

Returns

An Error indicating the success or failure of the function.

5.1.2.11 FLYCAPTURE2_C_API fc2Error fc2GetInterfaceTypeFromGuid (fc2Context context, fc2PGRGuid * pGuid, fc2InterfaceType * pInterfaceType)

Gets the interface type associated with a PGRGuid.

This is useful in situations where there is a need to enumerate all cameras for a particular interface.

Parameters

context	The fc2Context to be used.
pGuid	The PGRGuid to get the interface for.
pInterfaceType	The interface type of the PGRGuid.

Returns

5.1.2.12 FLYCAPTURE2_C_API fc2Error fc2GetNumOfCameras (fc2Context context, unsigned int * pNumCameras)

Gets the number of cameras attached to the PC.

Parameters

context	The fc2Context to be used.
pNumCameras	Number of cameras detected.

Returns

A fc2Error indicating the success or failure of the function.

5.1.2.13 FLYCAPTURE2_C_API fc2Error fc2GetNumOfDevices (fc2Context context, unsigned int * pNumDevices)

Gets the number of devices.

This may include hubs, host controllers and other hardware devices (including cameras).

context	The fc2Context to be used.
pNumDevices	The number of devices found.

Returns

An Error indicating the success or failure of the function.

5.1.2.14 FLYCAPTURE2_C_API fc2Error fc2GetTopology (fc2Context context, fc2TopologyNodeContext * pTopologyNodeContext)

Gets the topology information for the PC.

Parameters

context		The fc2Context to be used.
pTopology	NodeContext	A Topology Node context that will contain the topology information

Returns

An Error indicating the success or failure of the function.

5.1.2.15 FLYCAPTURE2_C_API fc2Error fc2GetUsbLinkInfo (fc2Context context, fc2PGRGuid guid, unsigned int * pValue)

Read usb link info for the port that the specified device is connected to.

Parameters

context	The fc2Context to be used.
guid	Unique PGRGuid for the device.
pValue	Value read from the card register.

Returns

An Error indicating the success or failure of the function.

5.1.2.16 FLYCAPTURE2_C_API fc2Error fc2GetUsbPortStatus (fc2Context context, fc2PGRGuid guid, unsigned int * pValue*)

Read usb port status for the port that the specified device is connected to.

context	The fc2Context to be used.
guid	Unique PGRGuid for the device.
pValue	Value read from the card register.

Returns

An Error indicating the success or failure of the function.

5.1.2.17 FLYCAPTURE2_C_API fc2Error fc2lsCameraControlable (fc2Context context, fc2PGRGuid * pGuid, BOOL * pControlable)

Query whether a GigE camera is controllable.

Parameters

context	The fc2Context to be used.
pGuid	Unique PGRGuid for the camera.
pControllable	True indicates camera is controllable

Returns

A fc2Error indicating the success or failure of the function.

5.1.2.18 FLYCAPTURE2_C_API fc2Error fc2ReadPhyRegister (fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int *pValue*)

Read a phy register on the specified device.

The full address to be read from is determined by the page, port and address.

Parameters

context	The fc2Context to be used.
guid	Unique PGRGuid for the device.
page	Page to read from.
port	Port to read from.
address	Address to read from.
pValue	Value read from the phy register.

Returns

An Error indicating the success or failure of the function.

5.1.2.19 FLYCAPTURE2_C_API fc2Error fc2RegisterCallback (fc2Context, fc2BusEventCallback enumCallback, fc2BusCallbackType callbackType, void * pParameter, fc2CallbackHandle * pCallbackHandle)

Register a callback function that will be called when the specified callback event occurs.

Parameters

context	The fc2Context to be used.
enumCallback	Pointer to function that will receive the callback.
callbackType	Type of callback to register for.
pParameter	Callback parameter to be passed to callback.
pCallbackHandle	Unique callback handle used for unregistering callback.

Returns

A fc2Error indicating the success or failure of the function.

5.1.2.20 FLYCAPTURE2_C_API fc2Error fc2RescanBus (fc2Context context)

Force a rescan of the buses.

This does not trigger a bus reset. However, any current connections to a Camera object will be invalidated.

Returns

An Error indicating the success or failure of the function.

5.1.2.21 FLYCAPTURE2_C_API fc2Error fc2UnregisterCallback (fc2Context *context*, fc2CallbackHandle *callbackHandle*)

Unregister a callback function.

Parameters

context	The fc2Context to be used.
callbackHandle	Unique callback handle.

Returns

A fc2Error indicating the success or failure of the function.

5.1.2.22 FLYCAPTURE2_C_API fc2Error fc2WritePhyRegister (fc2Context context, fc2PGRGuid guid, unsigned int page, unsigned int port, unsigned int address, unsigned int value)

Write a phy register on the specified device.

The full address to be written to is determined by the page, port and address.

context The fc2Context to be used.

Parameters

guid	Unique PGRGuid for the device.
page	Page to write to.
port	Port to write to.
address	Address to write to.
value	Value to write to phy register.

Returns

5.2 Connection and Image Retrieval

These functions deal with connections and image retrieval from the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2Connect (fc2Context context, fc2PGRGuid *guid)

Connects the camera object to the camera specified by the GUID.

FLYCAPTURE2 C API fc2Error fc2Disconnect (fc2Context context)

Disconnects the fc2Context from the camera.

FLYCAPTURE2_C_API fc2Error fc2SetCallback (fc2Context context, fc2ImageEventCallback pCallbackFn, void *pCallbackData)

Sets the callback data to be used on completion of image transfer.

• FLYCAPTURE2 C API fc2Error fc2StartCapture (fc2Context context)

Starts isochronous image capture.

• FLYCAPTURE2_C_API fc2Error fc2StartCaptureCallback (fc2Context context, fc2ImageEventCallback p← CallbackFn, void *pCallbackData)

Starts isochronous image capture.

• FLYCAPTURE2_C_API fc2Error fc2StartSyncCapture (unsigned int numCameras, fc2Context *pContexts)

Starts synchronized isochronous image capture on multiple cameras.

FLYCAPTURE2_C_API fc2Error fc2StartSyncCaptureCallback (unsigned int numCameras, fc2Context *p←
 Contexts, fc2ImageEventCallback *pCallbackFns, void **pCallbackDataArray)

Starts synchronized isochronous image capture on multiple cameras.

• FLYCAPTURE2_C_API fc2Error fc2RetrieveBuffer (fc2Context context, fc2Image *pImage)

Retrieves the next image object containing the next image.

FLYCAPTURE2_C_API fc2Error fc2StopCapture (fc2Context context)

Stops isochronous image transfer and cleans up all associated resources.

FLYCAPTURE2_C_API fc2Error fc2WaitForBufferEvent (fc2Context context, fc2Image *pImage, unsigned int eventNumber)

Retrieves the next image event containing the next part of the image.

• FLYCAPTURE2_C_API fc2Error fc2SetUserBuffers (fc2Context context, unsigned char *const ppMem← Buffers, int size, int nNumBuffers)

Specify user allocated buffers to use as image data buffers.

FLYCAPTURE2_C_API fc2Error fc2GetConfiguration (fc2Context context, fc2Config *config)

Get the configuration associated with the camera.

FLYCAPTURE2_C_API fc2Error fc2SetConfiguration (fc2Context context, fc2Config *config)

Set the configuration associated with the camera.

5.2.1 Detailed Description

These functions deal with connections and image retrieval from the camera.

5.2.2 Function Documentation

5.2.2.1 FLYCAPTURE2 C API fc2Error fc2Connect (fc2Context context, fc2PGRGuid * guid)

Connects the camera object to the camera specified by the GUID.

Parameters

context	The fc2Context to be used.
guid	The unique identifier for a specific camera on the PC.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.2 FLYCAPTURE2_C_API fc2Error fc2Disconnect (fc2Context context)

Disconnects the fc2Context from the camera.

Parameters

context	The fc2Context to be used.
---------	----------------------------

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.3 FLYCAPTURE2_C_API fc2Error fc2GetConfiguration (fc2Context context, fc2Config * config)

Get the configuration associated with the camera.

See also

fc2SetConfiguration()

Parameters

context	The fc2Context to be used.
config	Pointer to the configuration structure to be filled.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.4 FLYCAPTURE2_C_API fc2Error fc2RetrieveBuffer (fc2Context context, fc2Image * plmage)

Retrieves the next image object containing the next image.

See also

fc2StartCapture()
fc2StopCapture()

Parameters

context	The fc2Context to be used.
plmage	Pointer to fc2Image to store image data.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.5 FLYCAPTURE2_C_API fc2Error fc2SetCallback (fc2Context *context*, fc2ImageEventCallback *pCallbackFn*, void * *pCallbackData*)

Sets the callback data to be used on completion of image transfer.

To clear the current stored callback data, pass in NULL for both callback arguments.

See also

fc2StartCapture()

Parameters

context	The fc2Context to be used.
pCallbackFn	A function to be called when a new image is received.
pCallbackData	A pointer to data that can be passed to the callback function.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.6 FLYCAPTURE2_C_API fc2Error fc2SetConfiguration (fc2Context context, fc2Config * config)

Set the configuration associated with the camera.

See also

fc2GetConfiguration()

Parameters

context	The fc2Context to be used.
config	Pointer to the configuration structure to be used.

Returns

5.2.2.7 FLYCAPTURE2_C_API fc2Error fc2SetUserBuffers (fc2Context context, unsigned char *const ppMemBuffers, int size, int nNumBuffers)

Specify user allocated buffers to use as image data buffers.

To prevent image tearing, the size of each buffer should be equal to ((unsigned int)(bufferSize + packetSize - 1)/packetSize) * packetSize. The total size should be (size * numBuffers) or larger. The packet Size that should be used differs between interfaces: Firewire: Use the Format7 packet size. Usb2: First round to Format7 packet size then round to 512 bytes. Usb3: Use a packet size of 1024 bytes. GigE: No need to do any rounding on GigE

See also

fc2StartCapture()
fc2RetrieveBuffer()
fc2StopCapture()

Parameters

context	The fc2Context to be used.
ppMemBuffers	Pointer to memory buffers to be written to. The size of the data should be equal to (size * numBuffers) or larger.
size	The size of each buffer (in bytes).
nNumBuffers	Number of buffers in the array.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.8 FLYCAPTURE2_C_API fc2Error fc2StartCapture (fc2Context context)

Starts isochronous image capture.

It will use either the current video mode or the most recently set video mode of the camera.

See also

fc2RetrieveBuffer()
fc2StartSyncCapture()
fc2StopCapture()

Parameters

context	The fc2Context to be used.

Returns

5.2.2.9 FLYCAPTURE2_C_API fc2Error fc2StartCaptureCallback (fc2Context context, fc2ImageEventCallback pCallbackFn, void * pCallbackData)

Starts isochronous image capture.

It will use either the current video mode or the most recently set video mode of the camera. The callback function is called when a new image is received from the camera.

See also

fc2RetrieveBuffer()
fc2StartSyncCapture()
fc2StopCapture()

Parameters

context	The fc2Context to be used.
pCallbackFn	A function to be called when a new image is received.
pCallbackData	A pointer to data that can be passed to the callback function. A NULL pointer is acceptable.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.10 FLYCAPTURE2_C_API fc2Error fc2StartSyncCapture (unsigned int numCameras, fc2Context * pContexts)

Starts synchronized isochronous image capture on multiple cameras.

See also

fc2RetrieveBuffer() fc2StartCapture() fc2StopCapture()

Parameters

numCameras	Number of fc2Contexts in the ppCameras array.
pContexts	Array of fc2Contexts.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.11 FLYCAPTURE2_C_API fc2Error fc2StartSyncCaptureCallback (unsigned int numCameras, fc2Context * pContexts, fc2ImageEventCallback * pCallbackFns, void ** pCallbackDataArray)

Starts synchronized isochronous image capture on multiple cameras.

See also

```
fc2RetrieveBuffer()
fc2StartCapture()
fc2StopCapture()
```

Parameters

numCameras	Number of fc2Contexts in the ppCameras array.
pContexts	Array of fc2Contexts.
pCallbackFns	Array of callback functions for each camera.
pCallbackDataArray	Array of callback data pointers.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.12 FLYCAPTURE2_C_API fc2Error fc2StopCapture (fc2Context context)

Stops isochronous image transfer and cleans up all associated resources.

See also

fc2StartCapture()
fc2RetrieveBuffer()

Parameters

context	The fc2Context to be used.

Returns

A fc2Error indicating the success or failure of the function.

5.2.2.13 FLYCAPTURE2_C_API fc2Error fc2WaitForBufferEvent (fc2Context context, fc2Image * plmage, unsigned int eventNumber)

Retrieves the next image event containing the next part of the image.

See also

fc2StartCapture()
fc2RetrieveBuffer()
fc2StopCapture()

context	The fc2Context to be used.
plmage	Pointer to fc2lmage to store image data.
eventNumber	The event number to wait for.

5.3 Information and Properties

These functions deal with information and properties can be retrieved from the camera.

Functions

- FLYCAPTURE2_C_API fc2Error fc2GetCameraInfo (fc2Context context, fc2CameraInfo *pCameraInfo)

 Retrieves information from the camera such as serial number, model name and other camera information.
- FLYCAPTURE2_C_API fc2Error fc2GetPropertyInfo (fc2Context context, fc2PropertyInfo *propInfo)

 Retrieves information about the specified camera property.
- FLYCAPTURE2_C_API fc2Error fc2GetProperty (fc2Context context, fc2Property *prop)

Reads the settings for the specified property from the camera.

FLYCAPTURE2_C_API fc2Error fc2SetProperty (fc2Context context, fc2Property *prop)

Writes the settings for the specified property to the camera.

FLYCAPTURE2_C_API fc2Error fc2SetPropertyBroadcast (fc2Context context, fc2Property *prop)
 Writes the settings for the specified property to the camera.

5.3.1 Detailed Description

These functions deal with information and properties can be retrieved from the camera.

5.3.2 Function Documentation

5.3.2.1 FLYCAPTURE2 C API fc2Error fc2GetCameraInfo (fc2Context context, fc2CameraInfo * pCameraInfo)

Retrieves information from the camera such as serial number, model name and other camera information.

Parameters

context	The fc2Context to be used.
pCameraInfo	Pointer to the camera information structure to be filled.

Returns

A fc2Error indicating the success or failure of the function.

5.3.2.2 FLYCAPTURE2_C_API fc2Error fc2GetProperty (fc2Context context, fc2Property * prop)

Reads the settings for the specified property from the camera.

The property type must be specified in the fc2Property structure passed into the function in order for the function to succeed. If auto is on, the integer and abs values returned may not be consistent with each other.

See also

fc2GetPropertyInfo()
fc2SetProperty()

Parameters

context	The fc2Context to be used.
prop	Pointer to the Property structure to be filled.

Returns

A fc2Error indicating the success or failure of the function.

5.3.2.3 FLYCAPTURE2 C API fc2Error fc2GetPropertyInfo (fc2Context context, fc2PropertyInfo * propInfo)

Retrieves information about the specified camera property.

The property type must be specified in the fc2PropertyInfo structure passed into the function in order for the function to succeed.

See also

fc2GetProperty()
fc2SetProperty()

Parameters

context	The fc2Context to be used.
propInfo	Pointer to the PropertyInfo structure to be filled.

Returns

A fc2Error indicating the success or failure of the function.

5.3.2.4 FLYCAPTURE2_C_API fc2Error fc2SetProperty (fc2Context context, fc2Property * prop)

Writes the settings for the specified property to the camera.

The property type must be specified in the Property structure passed into the function in order for the function to succeed. The absControl flag controls whether the absolute or integer value is written to the camera. Use fc2GetPropertyInfo() to query which options are available for a specific property.

See also

fc2GetPropertyInfo()
fc2GetProperty()

context	The fc2Context to be used.
prop	Pointer to the Property structure to be used.

Returns

A fc2Error indicating the success or failure of the function.

5.3.2.5 FLYCAPTURE2_C_API fc2Error fc2SetPropertyBroadcast (fc2Context context, fc2Property * prop)

Writes the settings for the specified property to the camera.

The property type must be specified in the Property structure passed into the function in order for the function to succeed. The absControl flag controls whether the absolute or integer value is written to the camera.

Parameters

context	The fc2Context to be used.
prop	Pointer to the Property structure to be used.

Returns

5.4 General Purpose Input / Output

These functions deal with general GPIO pin control on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2GetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int *pDirection)

Get the GPIO pin direction for the specified pin.

• FLYCAPTURE2_C_API fc2Error fc2SetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

• FLYCAPTURE2_C_API fc2Error fc2SetGPIOPinDirectionBroadcast (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

5.4.1 Detailed Description

These functions deal with general GPIO pin control on the camera.

5.4.2 Function Documentation

5.4.2.1 FLYCAPTURE2_C_API fc2Error fc2GetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int * pDirection)

Get the GPIO pin direction for the specified pin.

This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

See also

fc2SetGPIOPinDirection()
fc2SetGPIOPinDirectionBroadcast()

Parameters

context	The fc2Context to be used.
pin	Pin to get the direction for.
pDirection	Direction of the pin. 0 for input, 1 for output.

Returns

5.4.2.2 FLYCAPTURE2_C_API fc2Error fc2SetGPIOPinDirection (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

This is useful if there is a need to set the pin into an input pin (i.e. to read the voltage) off the pin without setting it as a trigger source. This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

See also

fc2GetGPIOPinDirection()
fc2SetGPIOPinDirectionBroadcast()

Parameters

context	The fc2Context to be used.
pin	Pin to get the direction for.
direction	Direction of the pin. 0 for input, 1 for output.

Returns

A fc2Error indicating the success or failure of the function.

5.4.2.3 FLYCAPTURE2_C_API fc2Error fc2SetGPIOPinDirectionBroadcast (fc2Context context, unsigned int pin, unsigned int direction)

Set the GPIO pin direction for the specified pin.

This is useful if there is a need to set the pin into an input pin (i.e. to read the voltage) off the pin without setting it as a trigger source. This is not a required call when using the trigger or strobe functions as the pin direction is set automatically internally.

See also

fc2GetGPIOPinDirection()

Parameters

context	The fc2Context to be used.
pin	Pin to get the direction for.
direction	Direction of the pin. 0 for input, 1 for output.

Returns

5.5 Trigger 31

5.5 Trigger

These functions deal with trigger control on the camera.

Functions

Retrieve trigger information from the camera.

- FLYCAPTURE2_C_API fc2Error fc2GetTriggerMode (fc2Context context, fc2TriggerMode *triggerMode)

 Retrieve current trigger settings from the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetTriggerMode (fc2Context context, fc2TriggerMode *triggerMode)

 Set the specified trigger settings to the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetTriggerModeBroadcast (fc2Context context, fc2TriggerMode *triggerMode)

Set the specified trigger settings to the camera.

FLYCAPTURE2_C_API fc2Error fc2FireSoftwareTrigger (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2_C_API fc2Error fc2FireSoftwareTriggerBroadcast (fc2Context context)

Fire the software trigger according to the DCAM specifications.

FLYCAPTURE2_C_API fc2Error fc2GetTriggerDelayInfo (fc2Context context, fc2TriggerDelayInfo *trigger
 — DelayInfo)

Retrieve trigger delay information from the camera.

- FLYCAPTURE2_C_API fc2Error fc2GetTriggerDelay (fc2Context context, fc2TriggerDelay *triggerDelay)

 *Retrieve current trigger delay settings from the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelay (fc2Context context, fc2TriggerDelay *triggerDelay) Set the specified trigger delay settings to the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelayBroadcast (fc2Context context, fc2TriggerDelay *triggerDelay)

Set the specified trigger delay settings to the camera.

5.5.1 Detailed Description

These functions deal with trigger control on the camera.

5.5.2 Function Documentation

5.5.2.1 FLYCAPTURE2 C API fc2Error fc2FireSoftwareTrigger (fc2Context context)

Fire the software trigger according to the DCAM specifications.

context	The fc2Context to be used.

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.2 FLYCAPTURE2_C_API fc2Error fc2FireSoftwareTriggerBroadcast (fc2Context context)

Fire the software trigger according to the DCAM specifications.

Parameters

context	The fc2Context to be used.
---------	----------------------------

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.3 FLYCAPTURE2_C_API fc2Error fc2GetTriggerDelay (fc2Context context, fc2TriggerDelay * triggerDelay)

Retrieve current trigger delay settings from the camera.

See also

```
fc2GetTriggerModeInfo()
fc2GetTriggerMode()
fc2SetTriggerMode()
fc2GetTriggerDelayInfo()
fc2SetTriggerDelay()
fc2SetTriggerDelayBroadcast()
```

Parameters

context	The fc2Context to be used.
triggerDelay	Structure to receive trigger delay settings.

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.4 FLYCAPTURE2_C_API fc2Error fc2GetTriggerDelayInfo (fc2Context context, fc2TriggerDelayInfo * triggerDelayInfo)

Retrieve trigger delay information from the camera.

5.5 Trigger 33

See also

fc2GetTriggerModeInfo() fc2GetTriggerMode() fc2SetTriggerMode() fc2GetTriggerDelay() fc2SetTriggerDelay() fc2SetTriggerDelayBroadcast()

Parameters

context	The fc2Context to be used.
triggerDelayInfo	Structure to receive trigger delay information.

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.5 FLYCAPTURE2_C_API fc2Error fc2GetTriggerMode (fc2Context context, fc2TriggerMode * triggerMode)

Retrieve current trigger settings from the camera.

See also

fc2GetTriggerModeInfo() fc2SetTriggerMode() fc2SetTriggerModeBroadcast() fc2GetTriggerDelayInfo() fc2GetTriggerDelay() fc2SetTriggerDelay()

Parameters

context	The fc2Context to be used.
triggerMode	Structure to receive trigger mode settings.

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.6 FLYCAPTURE2_C_API fc2Error fc2GetTriggerModeInfo (fc2Context context, fc2TriggerModeInfo * triggerModeInfo)

Retrieve trigger information from the camera.

See also

fc2GetTriggerMode() fc2SetTriggerMode() fc2SetTriggerModeBroadcast() fc2GetTriggerDelayInfo() fc2GetTriggerDelay() fc2SetTriggerDelay()

Parameters

context	The fc2Context to be used.
triggerModeInfo	Structure to receive trigger information.

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.7 FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelay (fc2Context context, fc2TriggerDelay * triggerDelay)

Set the specified trigger delay settings to the camera.

See also

fc2GetTriggerModeInfo() fc2GetTriggerMode() fc2SetTriggerMode() fc2GetTriggerDelayInfo() fc2GetTriggerDelay() fc2SetTriggerDelayBroadcast()

Parameters

context	The fc2Context to be used.
triggerDelay	Structure providing trigger delay settings.

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.8 FLYCAPTURE2_C_API fc2Error fc2SetTriggerDelayBroadcast (fc2Context context, fc2TriggerDelay * triggerDelay)

Set the specified trigger delay settings to the camera.

5.5 Trigger 35

See also

fc2GetTriggerMode() fc2GetTriggerMode() fc2SetTriggerMode() fc2GetTriggerDelayInfo() fc2GetTriggerDelay() fc2SetTriggerDelay()

Parameters

context	The fc2Context to be used.
triggerDelay	Structure providing trigger delay settings.

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.9 FLYCAPTURE2_C_API fc2Error fc2SetTriggerMode (fc2Context context, fc2TriggerMode * triggerMode)

Set the specified trigger settings to the camera.

See also

fc2GetTriggerModeInfo() fc2GetTriggerMode() fc2GetTriggerDelayInfo() fc2GetTriggerDelay() fc2SetTriggerDelay() fc2SetTriggerModeBroadcast()

Parameters

context	The fc2Context to be used.
triggerMode	Structure providing trigger mode settings.

Returns

A fc2Error indicating the success or failure of the function.

5.5.2.10 FLYCAPTURE2_C_API fc2Error fc2SetTriggerModeBroadcast (fc2Context context, fc2TriggerMode * triggerMode)

Set the specified trigger settings to the camera.

See also

fc2GetTriggerModeInfo() fc2GetTriggerMode() fc2GetTriggerDelayInfo() fc2GetTriggerDelay() fc2SetTriggerDelay() fc2SetTriggerMode()

Parameters

context	The fc2Context to be used.
triggerMode	Structure providing trigger mode settings.

Returns

5.6 Strobe 37

5.6 Strobe

These functions deal with strobe control on the camera.

Functions

- FLYCAPTURE2_C_API fc2Error fc2GetStrobeInfo (fc2Context context, fc2StrobeInfo *strobeInfo)

 Retrieve strobe information from the camera.
- FLYCAPTURE2_C_API fc2Error fc2GetStrobe (fc2Context context, fc2StrobeControl *strobeControl)

 Retrieve current strobe settings from the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetStrobe (fc2Context context, fc2StrobeControl *strobeControl) Set current strobe settings to the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetStrobeBroadcast (fc2Context context, fc2StrobeControl *strobe ← Control)

Set current strobe settings to the camera.

5.6.1 Detailed Description

These functions deal with strobe control on the camera.

5.6.2 Function Documentation

5.6.2.1 FLYCAPTURE2_C_API fc2Error fc2GetStrobe (fc2Context context, fc2StrobeControl * strobeControl)

Retrieve current strobe settings from the camera.

The strobe pin must be specified in the structure before being passed in to the function.

See also

```
fc2GetStrobeInfo()
fc2SetStrobe()
fc2SetStrobeBroadcast()
```

Parameters

context	The fc2Context to be used.
strobeControl	Structure to receive strobe settings.

Returns

A fc2Error indicating the success or failure of the function.

5.6.2.2 FLYCAPTURE2 C API fc2Error fc2GetStrobeInfo (fc2Context context, fc2StrobeInfo * strobeInfo)

Retrieve strobe information from the camera.

See also

fc2GetStrobe()
fc2SetStrobeBroadcast()

Parameters

context	The fc2Context to be used.
strobeInfo	Structure to receive strobe information.

Returns

A fc2Error indicating the success or failure of the function.

5.6.2.3 FLYCAPTURE2_C_API fc2Error fc2SetStrobe (fc2Context context, fc2StrobeControl * strobeControl)

Set current strobe settings to the camera.

The strobe pin must be specified in the structure before being passed in to the function.

See also

fc2GetStrobeInfo()
fc2GetStrobe()
fc2SetStrobeBroadcast()

Parameters

context	The fc2Context to be used.
strobeControl	Structure providing strobe settings.

Returns

A fc2Error indicating the success or failure of the function.

5.6.2.4 FLYCAPTURE2_C_API fc2Error fc2SetStrobeBroadcast (fc2Context context, fc2StrobeControl * strobeControl)

Set current strobe settings to the camera.

The strobe pin must be specified in the structure before being passed in to the function.

See also

fc2GetStrobeInfo() fc2GetStrobe() fc2SetStrobe() 5.6 Strobe 39

Parameters

context	The fc2Context to be used.
strobeControl	Structure providing strobe settings.

Returns

5.7 Look Up Table

These functions deal with Look Up Table control on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2GetLUTInfo (fc2Context context, fc2LUTData *pData)

Query if LUT support is available on the camera.

 FLYCAPTURE2_C_API fc2Error fc2GetLUTBankInfo (fc2Context context, unsigned int bank, BOOL *p↔ ReadSupported, BOOL *pWriteSupported)

Query the read/write status of a single LUT bank.

• FLYCAPTURE2_C_API fc2Error fc2GetActiveLUTBank (fc2Context context, unsigned int *pActiveBank)

Get the LUT bank that is currently being used.

FLYCAPTURE2_C_API fc2Error fc2SetActiveLUTBank (fc2Context context, unsigned int activeBank)

Set the LUT bank that will be used.

• FLYCAPTURE2_C_API fc2Error fc2EnableLUT (fc2Context context, BOOL on)

Enable or disable LUT functionality on the camera.

• FLYCAPTURE2_C_API fc2Error fc2GetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int *pEntries)

Get the LUT channel settings from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int *pEntries)

Set the LUT channel settings to the camera.

5.7.1 Detailed Description

These functions deal with Look Up Table control on the camera.

5.7.2 Function Documentation

5.7.2.1 FLYCAPTURE2_C_API fc2Error fc2EnableLUT (fc2Context context, BOOL on)

Enable or disable LUT functionality on the camera.

See also

fc2GetLUTInfo()
fc2GetLUTChannel()
fc2SetLUTChannel()

context	The fc2Context to be used.
on	Whether to enable or disable LUT.

5.7 Look Up Table 41

Returns

A fc2Error indicating the success or failure of the function.

5.7.2.2 FLYCAPTURE2_C_API fc2Error fc2GetActiveLUTBank (fc2Context context, unsigned int * pActiveBank)

Get the LUT bank that is currently being used.

For cameras with PGR LUT, the active bank is always 0.

Parameters

context	The fc2Context to be used.
pActiveBank	The currently active bank.

Returns

A fc2Error indicating the success or failure of the function.

5.7.2.3 FLYCAPTURE2_C_API fc2Error fc2GetLUTBankInfo (fc2Context context, unsigned int bank, BOOL * pReadSupported, BOOL * pWriteSupported)

Query the read/write status of a single LUT bank.

Parameters

context	The fc2Context to be used.
bank	The bank to query.
pReadSupported	Whether reading from the bank is supported.
pWriteSupported	Whether writing to the bank is supported.

Returns

A fc2Error indicating the success or failure of the function.

5.7.2.4 FLYCAPTURE2_C_API fc2Error fc2GetLUTChannel (fc2Context context, unsigned int bank, unsigned int channel, unsigned int sizeEntries, unsigned int * pEntries*)

Get the LUT channel settings from the camera.

See also

fc2GetLUTInfo()
fc2EnableLUT()
fc2SetLUTChannel()

Parameters

context	The fc2Context to be used.
bank	Bank to retrieve.
channel	Channel to retrieve.
sizeEntries	Number of entries in LUT table to read.
pEntries	Array to store LUT entries.

Returns

A fc2Error indicating the success or failure of the function.

5.7.2.5 FLYCAPTURE2 C API fc2Error fc2GetLUTInfo (fc2Context context, fc2LUTData * pData)

Query if LUT support is available on the camera.

Note that some cameras may report support for the LUT and return an inputBitDepth of 0. In these cases use log2(numEntries) for the inputBitDepth.

See also

fc2EnableLUT()
fc2GetLUTChannel()
fc2SetLUTChannel()

Parameters

context	The fc2Context to be used.
pData	The LUT structure to be filled.

Returns

A fc2Error indicating the success or failure of the function.

5.7.2.6 FLYCAPTURE2_C_API fc2Error fc2SetActiveLUTBank (fc2Context context, unsigned int activeBank)

Set the LUT bank that will be used.

Parameters

context	The fc2Context to be used.
activeBank	The bank to be set as active.

Returns

5.7 Look Up Table 43

5.7.2.7 FLYCAPTURE2_C_API fc2Error fc2SetLUTChannel (fc2Context *context*, unsigned int *bank*, unsigned int *channel*, unsigned int *sizeEntries*, unsigned int * *pEntries*)

Set the LUT channel settings to the camera.

See also

fc2GetLUTInfo()
fc2EnableLUT()
fc2GetLUTChannel()

Parameters

context	The fc2Context to be used.	
bank	Bank to set.	
channel	Channel to set.	
sizeEntries	Number of entries in LUT table to write. This must be the same size as numEntries returned by GetLutInfo().	
pEntries	Array containing LUT entries to write.	

Returns

5.8 Memory Channels

These functions deal with memory channel control on the camera.

Functions

FLYCAPTURE2_C_API fc2Error fc2GetMemoryChannel (fc2Context context, unsigned int *pCurrent
 — Channel)

Retrieve the current memory channel from the camera.

- FLYCAPTURE2_C_API fc2Error fc2SaveToMemoryChannel (fc2Context context, unsigned int channel) Save the current settings to the specified current memory channel.
- FLYCAPTURE2_C_API fc2Error fc2RestoreFromMemoryChannel (fc2Context context, unsigned int channel)

 Restore the specified current memory channel.
- FLYCAPTURE2_C_API fc2Error fc2GetMemoryChannelInfo (fc2Context context, unsigned int *pNum← Channels)

Query the camera for memory channel support.

FLYCAPTURE2_C_API fc2Error fc2GetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo *pInfo)

Get the current status of the embedded image information register, as well as the availability of each embedded property.

FLYCAPTURE2_C_API fc2Error fc2SetEmbeddedImageInfo (fc2Context context, fc2EmbeddedImageInfo *pInfo)

Sets the on/off values of the embedded image information structure to the camera.

5.8.1 Detailed Description

These functions deal with memory channel control on the camera.

5.8.2 Function Documentation

5.8.2.1 FLYCAPTURE2_C_API fc2Error fc2GetEmbeddedImageInfo (fc2Context *context*, fc2EmbeddedImageInfo * pInfo)

Get the current status of the embedded image information register, as well as the availability of each embedded property.

See also

fc2SetEmbeddedImageInfo()

context	The fc2Context to be used.
pInfo	Structure to be filled.

5.8 Memory Channels 45

Returns

A fc2Error indicating the success or failure of the function.

5.8.2.2 FLYCAPTURE2_C_API fc2Error fc2GetMemoryChannel (fc2Context context, unsigned int * pCurrentChannel)

Retrieve the current memory channel from the camera.

See also

fc2SaveToMemoryChannel()
fc2RestoreFromMemoryChannel()
fc2GetMemoryChannelInfo()

Parameters

context	The fc2Context to be used.
pCurrentChannel	Current memory channel.

Returns

A fc2Error indicating the success or failure of the function.

5.8.2.3 FLYCAPTURE2_C_API fc2Error fc2GetMemoryChannelInfo (fc2Context context, unsigned int * pNumChannels)

Query the camera for memory channel support.

If the number of channels are 0, then memory channel support is not available.

See also

fc2GetMemoryChannel()
fc2SaveToMemoryChannel()
fc2RestoreFromMemoryChannel()

Parameters

ĺ	context	The fc2Context to be used.
	pNumChannels	Number of memory channels supported.

Returns

A fc2Error indicating the success or failure of the function.

5.8.2.4 FLYCAPTURE2 C API fc2Error fc2RestoreFromMemoryChannel (fc2Context context, unsigned int channel)

Restore the specified current memory channel.

See also

fc2GetMemoryChannel() fc2SaveToMemoryChannel() fc2GetMemoryChannelInfo()

Parameters

context	The fc2Context to be used.
channel	Memory channel to restore from.

Returns

A fc2Error indicating the success or failure of the function.

5.8.2.5 FLYCAPTURE2_C_API fc2Error fc2SaveToMemoryChannel (fc2Context context, unsigned int channel)

Save the current settings to the specified current memory channel.

See also

fc2GetMemoryChannel()
fc2RestoreFromMemoryChannel()
fc2GetMemoryChannelInfo()

Parameters

context	The fc2Context to be used.
channel	Memory channel to save to.

Returns

A fc2Error indicating the success or failure of the function.

5.8.2.6 FLYCAPTURE2_C_API fc2Error fc2SetEmbeddedImageInfo (fc2Context *context*, fc2EmbeddedImageInfo * pInfo)

Sets the on/off values of the embedded image information structure to the camera.

See also

fc2GetEmbeddedImageInfo()

context	The fc2Context to be used.
pInfo	Structure to be used.

5.8 Memory Channels 47

5.9 Register Operation

These functions deal with register operation on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2WriteRegister (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera.

 FLYCAPTURE2_C_API fc2Error fc2ReadRegister (fc2Context context, unsigned int address, unsigned int *pValue)

Read the specified register from the camera.

FLYCAPTURE2_C_API fc2Error fc2WriteRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera with broadcast.

• FLYCAPTURE2_C_API fc2Error fc2WriteRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, const unsigned int *pBuffer, unsigned int length)

Write to the specified register block on the camera.

 FLYCAPTURE2_C_API fc2Error fc2ReadRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, unsigned int *pBuffer, unsigned int length)

Write to the specified register block on the camera.

• FLYCAPTURE2 C API const char * fc2GetRegisterString (unsigned int registerVal)

Returns a text representation of the register value.

5.9.1 Detailed Description

These functions deal with register operation on the camera.

5.9.2 Function Documentation

5.9.2.1 FLYCAPTURE2_C_API const char* fc2GetRegisterString (unsigned int registerVal)

Returns a text representation of the register value.

Parameters

registerVal	The register value to query.

Returns

A fc2Error indicating the success or failure of the function.

5.9.2.2 FLYCAPTURE2_C_API fc2Error fc2ReadRegister (fc2Context context, unsigned int address, unsigned int * pValue)

Read the specified register from the camera.

See also

fc2WriteRegister()

Parameters

context	The fc2Context to be used.
address	DCAM address to be read from.
pValue	The value that is read.

Returns

A fc2Error indicating the success or failure of the function.

5.9.2.3 FLYCAPTURE2_C_API fc2Error fc2ReadRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, unsigned int *pBuffer*, unsigned int length)

Write to the specified register block on the camera.

See also

fc2WriteRegisterBlock()

Parameters

context	The fc2Context to be used.
addressHigh	Top 16 bits of the 48-bit absolute address to read from.
addressLow	Bottom 32 bits of the 48 bits absolute address to read from.
pBuffer	Array to store read data.
length	Size of array, in quadlets.

Returns

A fc2Error indicating the success or failure of the function.

5.9.2.4 FLYCAPTURE2_C_API fc2Error fc2WriteRegister (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera.

See also

fc2ReadRegister()

Parameters

context	The fc2Context to be used.
address	DCAM address to be written to.
value	The value to be written.

Generated by Doxygen

Returns

A fc2Error indicating the success or failure of the function.

5.9.2.5 FLYCAPTURE2_C_API fc2Error fc2WriteRegisterBlock (fc2Context context, unsigned short addressHigh, unsigned int addressLow, const unsigned int * pBuffer, unsigned int length)

Write to the specified register block on the camera.

See also

fc2ReadRegisterBlock()

Parameters

context	The fc2Context to be used.
addressHigh	Top 16 bits of the 48-bit absolute address to write to.
addressLow	Bottom 32 bits of the 48 bits absolute address to write to.
pBuffer	Array containing data to be written.
length	Size of array, in quadlets.

Returns

A fc2Error indicating the success or failure of the function.

5.9.2.6 FLYCAPTURE2_C_API fc2Error fc2WriteRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write to the specified register on the camera with broadcast.

See also

fc2ReadRegisterBlock()

Parameters

context	The fc2Context to be used.
address	DCAM address to be written to.
value	The value to be written.

Returns

5.10 DCAM Formats 51

5.10 DCAM Formats

These functions deal with DCAM video mode and frame rate on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2GetVideoModeAndFrameRateInfo (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate, BOOL *pSupported)

Query the camera to determine if the specified video mode and frame rate is supported.

 FLYCAPTURE2_C_API fc2Error fc2GetVideoModeAndFrameRate (fc2Context context, fc2VideoMode *videoMode, fc2FrameRate *frameRate)

Get the current video mode and frame rate from the camera.

• FLYCAPTURE2_C_API fc2Error fc2SetVideoModeAndFrameRate (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate)

Set the specified video mode and frame rate to the camera.

5.10.1 Detailed Description

These functions deal with DCAM video mode and frame rate on the camera.

5.10.2 Function Documentation

5.10.2.1 FLYCAPTURE2_C_API fc2Error fc2GetVideoModeAndFrameRate (fc2Context context, fc2VideoMode * videoMode, fc2FrameRate * frameRate)

Get the current video mode and frame rate from the camera.

If the camera is in Format7, the video mode will be VIDEOMODE_FORMAT7 and the frame rate will be FRAME← RATE_FORMAT7.

Parameters

context	The fc2Context to be used.
videoMode	Current video mode.
frameRate	Current frame rate.

Returns

A fc2Error indicating the success or failure of the function.

5.10.2.2 FLYCAPTURE2_C_API fc2Error fc2GetVideoModeAndFrameRateInfo (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate, BOOL * pSupported)

Query the camera to determine if the specified video mode and frame rate is supported.

Parameters

context	The fc2Context to be used.
videoMode	Video mode to check.
frameRate	Frame rate to check.
pSupported	Whether the video mode and frame rate is supported.

Returns

A fc2Error indicating the success or failure of the function.

5.10.2.3 FLYCAPTURE2_C_API fc2Error fc2SetVideoModeAndFrameRate (fc2Context context, fc2VideoMode videoMode, fc2FrameRate frameRate)

Set the specified video mode and frame rate to the camera.

It is not possible to set the camera to VIDEOMODE_FORMAT7 or FRAMERATE_FORMAT7. Use the Format7 functions to set the camera into Format7.

Parameters

con	itext	The fc2Context to be used.
vide	eoMode	Video mode to set to camera.
frar	neRate	Frame rate to set to camera.

Returns

5.11 Format7 53

5.11 Format7

These functions deal with Format7 custom image control on the camera.

Functions

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

 FLYCAPTURE2_C_API fc2Error fc2ValidateFormat7Settings (fc2Context context, fc2Format7ImageSettings *imageSettings, BOOL *settingsAreValid, fc2Format7PacketInfo)

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

FLYCAPTURE2_C_API fc2Error fc2GetFormat7Configuration (fc2Context context, fc2Format7Image
 — Settings *imageSettings, unsigned int *packetSize, float *percentage)

Get the current Format7 configuration from the camera.

FLYCAPTURE2_C_API fc2Error fc2SetFormat7ConfigurationPacket (fc2Context context, fc2Format7← ImageSettings *imageSettings, unsigned int packetSize)

Set the current Format7 configuration to the camera.

 FLYCAPTURE2_C_API fc2Error fc2SetFormat7Configuration (fc2Context context, fc2Format7ImageSettings *imageSettings, float percentSpeed)

Set the current Format7 configuration to the camera.

5.11.1 Detailed Description

These functions deal with Format7 custom image control on the camera.

5.11.2 Function Documentation

5.11.2.1 FLYCAPTURE2_C_API fc2Error fc2GetFormat7Configuration (fc2Context context, fc2Format7ImageSettings * imageSettings, unsigned int * packetSize, float * percentage)

Get the current Format7 configuration from the camera.

This call will only succeed if the camera is already in Format7.

Parameters

context	The fc2Context to be used.
imageSettings	Current image settings.
packetSize	Current packet size.
percentage	Current packet size as a percentage.

Returns

5.11.2.2 FLYCAPTURE2_C_API fc2Error fc2GetFormat7Info (fc2Context context, fc2Format7Info * info, BOOL * pSupported)

Retrieve the availability of Format7 custom image mode and the camera capabilities for the specified Format7 mode.

The mode must be specified in the Format7Info structure in order for the function to succeed.

Parameters

context	The fc2Context to be used.	
info	Structure to be filled with the capabilities of the specified mode and the current state in the specified mode.	
pSupported	Whether the specified mode is supported.	

Returns

A fc2Error indicating the success or failure of the function.

5.11.2.3 FLYCAPTURE2_C_API fc2Error fc2SetFormat7Configuration (fc2Context context, fc2Format7ImageSettings * imageSettings, float percentSpeed)

Set the current Format7 configuration to the camera.

Parameters

context	The fc2Context to be used.
imageSettings	Image settings to be written to the camera.
percentSpeed	Packet size as a percentage to be written to the camera.

Returns

A fc2Error indicating the success or failure of the function.

5.11.2.4 FLYCAPTURE2_C_API fc2Error fc2SetFormat7ConfigurationPacket (fc2Context context, fc2Format7ImageSettings * imageSettings, unsigned int packetSize)

Set the current Format7 configuration to the camera.

Parameters

context	The fc2Context to be used.
imageSettings	Image settings to be written to the camera.
packetSize	Packet size to be written to the camera.

Returns

5.11 Format7 55

5.11.2.5 FLYCAPTURE2_C_API fc2Error fc2ValidateFormat7Settings (fc2Context context, fc2Format7ImageSettings * imageSettings, BOOL * settingsAreValid, fc2Format7PacketInfo * packetInfo)

Validates Format7ImageSettings structure and returns valid packet size information if the image settings are valid.

The current image settings are cached while validation is taking place. The cached settings are restored when validation is complete.

Parameters

context	The fc2Context to be used.
imageSettings	Structure containing the image settings.
settingsAreValid	Whether the settings are valid.
packetInfo	Packet size information that can be used to determine a valid packet size.

Returns

5.12 GVCP Register Operation

These functions deal with GVCP register operation on the camera.

Functions

• FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegister (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register.

FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register with broadcast.

• FLYCAPTURE2_C_API fc2Error fc2ReadGVCPRegister (fc2Context context, unsigned int address, unsigned int *pValue)

Read a GVCP register.

• FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegisterBlock (fc2Context context, unsigned int address, const unsigned int *pBuffer, unsigned int length)

Write a GVCP register block.

FLYCAPTURE2_C_API fc2Error fc2ReadGVCPRegisterBlock (fc2Context context, unsigned int address, unsigned int *pBuffer, unsigned int length)

Read a GVCP register block.

• FLYCAPTURE2_C_API fc2Error fc2WriteGVCPMemory (fc2Context context, unsigned int address, const unsigned char *pBuffer, unsigned int length)

Write a GVCP memory block.

FLYCAPTURE2_C_API fc2Error fc2ReadGVCPMemory (fc2Context context, unsigned int address, unsigned char *pBuffer, unsigned int length)

Read a GVCP memory block.

5.12.1 Detailed Description

These functions deal with GVCP register operation on the camera.

5.12.2 Function Documentation

5.12.2.1 FLYCAPTURE2_C_API fc2Error fc2ReadGVCPMemory (fc2Context context, unsigned int address, unsigned char * pBuffer, unsigned int length)

Read a GVCP memory block.

context	The fc2Context to be used.
address	GVCP address to be read from.
pBuffer	Array containing data to be written.
length	Size of array, in quadlets.

Returns

An Error indicating the success or failure of the function.

5.12.2.2 FLYCAPTURE2_C_API fc2Error fc2ReadGVCPRegister (fc2Context context, unsigned int address, unsigned int * pValue)

Read a GVCP register.

Parameters

context	The fc2Context to be used.
address	GVCP address to be read from.
pValue	The value that is read.

Returns

An Error indicating the success or failure of the function.

5.12.2.3 FLYCAPTURE2_C_API fc2Error fc2ReadGVCPRegisterBlock (fc2Context context, unsigned int address, unsigned int * pBuffer, unsigned int length)

Read a GVCP register block.

Parameters

context	The fc2Context to be used.	
address	GVCP address to be read from.	
pBuffer	Array containing data to be written.	
length	Size of array, in quadlets.	

Returns

An Error indicating the success or failure of the function.

5.12.2.4 FLYCAPTURE2_C_API fc2Error fc2WriteGVCPMemory (fc2Context context, unsigned int address, const unsigned char * pBuffer, unsigned int length)

Write a GVCP memory block.

context	The fc2Context to be used.	
address	GVCP address to be write to.	
pBuffer	Array containing data to be written.	
length	Size of array, in quadlets.	

Returns

An Error indicating the success or failure of the function.

5.12.2.5 FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegister (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register.

Parameters

context	The fc2Context to be used.
address	GVCP address to be written to.
value	The value to be written.

Returns

An Error indicating the success or failure of the function.

5.12.2.6 FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegisterBlock (fc2Context context, unsigned int address, const unsigned int * pBuffer, unsigned int length)

Write a GVCP register block.

Parameters

context	The fc2Context to be used.	
address	GVCP address to be write to.	
pBuffer	Array containing data to be written.	
length	Size of array, in quadlets.	

Returns

An Error indicating the success or failure of the function.

5.12.2.7 FLYCAPTURE2_C_API fc2Error fc2WriteGVCPRegisterBroadcast (fc2Context context, unsigned int address, unsigned int value)

Write a GVCP register with broadcast.

context	The fc2Context to be used.	
address	GVCP address to be written to.	
value	The value to be written.	

5.13 GigE property manipulation

These functions deal with GigE properties.

Functions

- FLYCAPTURE2_C_API fc2Error fc2GetGigEProperty (fc2Context context, fc2GigEProperty *pGigEProp)

 Get the specified GigEProperty.
- FLYCAPTURE2_C_API fc2Error fc2SetGigEProperty (fc2Context context, const fc2GigEProperty *pGigE←
 Prop)

Set the specified GigEProperty.

• FLYCAPTURE2_C_API fc2Error fc2DiscoverGigEPacketSize (fc2Context context, unsigned int *packetSize)

Discover the largest packet size that works for the network link between the PC and the camera.

5.13.1 Detailed Description

These functions deal with GigE properties.

5.13.2 Function Documentation

5.13.2.1 FLYCAPTURE2_C_API fc2Error fc2DiscoverGigEPacketSize (fc2Context context, unsigned int * packetSize)

Discover the largest packet size that works for the network link between the PC and the camera.

This is useful in cases where there may be multiple links between the PC and the camera and there is a possibility of a component not supporting the recommended jumbo frame packet size of 9000.

Parameters

context	The fc2Context to be used.
packetSize	The maximum packet size supported by the link.

Returns

An Error indicating the success or failure of the function.

5.13.2.2 FLYCAPTURE2_C_API fc2Error fc2GetGigEProperty (fc2Context context, fc2GigEProperty * pGigEProp)

Get the specified GigEProperty.

The GigEPropertyType field must be set in order for this function to succeed.

context	The fc2Context to be used.
pGigEProp	The GigE property to get.

Returns

An Error indicating the success or failure of the function.

5.13.2.3 FLYCAPTURE2_C_API fc2Error fc2SetGigEProperty (fc2Context context, const fc2GigEProperty * pGigEProp)

Set the specified GigEProperty.

The GigEPropertyType field must be set in order for this function to succeed.

Parameters

context	The fc2Context to be used.
pGigEProp	The GigE property to set.

Returns

5.14 GigE image settings

These functions deal with GigE image setting.

Functions

 FLYCAPTURE2_C_API fc2Error fc2QueryGigElmagingMode (fc2Context context, fc2Mode mode, BOOL *isSupported)

Check if the particular imaging mode is supported by the camera.

- FLYCAPTURE2_C_API fc2Error fc2GetGigEImagingMode (fc2Context context, fc2Mode *mode)
 - Get the current imaging mode on the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetGigEImagingMode (fc2Context context, fc2Mode mode)

Set the current imaging mode to the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEImageSettingsInfo (fc2Context context, fc2GigEImage
 SettingsInfo *pInfo)

Get information about the image settings possible on the camera.

FLYCAPTURE2_C_API fc2Error fc2GetGigEImageSettings (fc2Context context, fc2GigEImageSettings *p↔
ImageSettings)

Get the current image settings on the camera.

FLYCAPTURE2_C_API fc2Error fc2SetGigEImageSettings (fc2Context context, const fc2GigEImageSettings *pImageSettings)

Set the image settings specified to the camera.

5.14.1 Detailed Description

These functions deal with GigE image setting.

5.14.2 Function Documentation

5.14.2.1 FLYCAPTURE2_C_API fc2Error fc2GetGigElmageSettings (fc2Context context, fc2GigElmageSettings * plmageSettings)

Get the current image settings on the camera.

Parameters

context	The fc2Context to be used.
plmageSettings	Current image settings on camera.

Returns

An Error indicating the success or failure of the function.

5.14.2.2 FLYCAPTURE2_C_API fc2Error fc2GetGigEImageSettingsInfo (fc2Context context, fc2GigEImageSettingsInfo * pInfo)

Get information about the image settings possible on the camera.

Parameters

context	The fc2Context to be used.
pInfo	Image settings information.

Returns

An Error indicating the success or failure of the function.

5.14.2.3 FLYCAPTURE2_C_API fc2Error fc2GetGigEImagingMode (fc2Context context, fc2Mode * mode)

Get the current imaging mode on the camera.

Parameters

context	The fc2Context to be used.
mode	Current imaging mode on the camera.

Returns

An Error indicating the success or failure of the function.

5.14.2.4 FLYCAPTURE2_C_API fc2Error fc2QueryGigElmagingMode (fc2Context context, fc2Mode mode, BOOL * isSupported)

Check if the particular imaging mode is supported by the camera.

Parameters

context	The fc2Context to be used.
mode	The mode to check.
isSupported	Whether the mode is supported.

Returns

An Error indicating the success or failure of the function.

5.14.2.5 FLYCAPTURE2_C_API fc2Error fc2SetGigEImageSettings (fc2Context context, const fc2GigEImageSettings * plmageSettings)

Set the image settings specified to the camera.

context	The fc2Context to be used.
plmageSettings	Image settings to set to camera.

Returns

An Error indicating the success or failure of the function.

5.14.2.6 FLYCAPTURE2_C_API fc2Error fc2SetGigElmagingMode (fc2Context context, fc2Mode mode)

Set the current imaging mode to the camera.

This should only be done when the camera is not streaming images.

Parameters

context	The fc2Context to be used.
mode	Imaging mode to set to the camera.

Returns

5.15 GigE image binning settings

These functions deal with GigE image binning settings.

Functions

• FLYCAPTURE2_C_API fc2Error fc2GetGigEImageBinningSettings (fc2Context context, unsigned int *horz ← BinnningValue, unsigned int *vertBinnningValue)

Get the current binning settings on the camera.

FLYCAPTURE2_C_API fc2Error fc2SetGigEImageBinningSettings (fc2Context context, unsigned int horz
 —
 BinnningValue, unsigned int vertBinnningValue)

Set the specified binning values to the camera.

5.15.1 Detailed Description

These functions deal with GigE image binning settings.

5.15.2 Function Documentation

5.15.2.1 FLYCAPTURE2_C_API fc2Error fc2GetGigElmageBinningSettings (fc2Context context, unsigned int * horzBinnningValue, unsigned int * vertBinnningValue)

Get the current binning settings on the camera.

Parameters

context	The fc2Context to be used.
horzBinnningValue	Current horizontal binning value.
vertBinnningValue	Current vertical binning value.

Returns

An Error indicating the success or failure of the function.

5.15.2.2 FLYCAPTURE2_C_API fc2Error fc2SetGigEImageBinningSettings (fc2Context context, unsigned int horzBinnningValue, unsigned int vertBinnningValue)

Set the specified binning values to the camera.

It is recommended that GetGigEImageSettingsInfo() be called after this function succeeds to retrieve the new image settings information for the new binning mode.

context	The fc2Context to be used.
horzBinnningValue	Horizontal binning value.
vertBinnningValue	Vertical binning value.
	_

Returns

5.16 GigE image stream configuration

These functions deal with GigE image stream configuration.

Functions

FLYCAPTURE2_C_API fc2Error fc2GetNumStreamChannels (fc2Context context, unsigned int *num← Channels)

Get the number of stream channels present on the camera.

• FLYCAPTURE2_C_API fc2Error fc2GetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel *pChannel)

Get the stream channel information for the specified channel.

• FLYCAPTURE2_C_API fc2Error fc2SetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel *pChannel)

Set the stream channel information for the specified channel.

- FLYCAPTURE2_C_API fc2Error fc2GetGigEConfig (fc2Context context, fc2GigEConfig *pConfig)

 Get the current gige config on the camera.
- FLYCAPTURE2_C_API fc2Error fc2SetGigEConfig (fc2Context context, const fc2GigEConfig *pConfig)

 Set the gige config specified to the camera.

5.16.1 Detailed Description

These functions deal with GigE image stream configuration.

5.16.2 Function Documentation

5.16.2.1 FLYCAPTURE2 C API fc2Error fc2GetGigEConfig (fc2Context context, fc2GigEConfig * pConfig)

Get the current gige config on the camera.

Parameters

context	The fc2Context to be used.
pGigEConfig	Current configuration on camera.

Returns

An Error indicating the success or failure of the function.

5.16.2.2 FLYCAPTURE2_C_API fc2Error fc2GetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel * pChannel)

Get the stream channel information for the specified channel.

Parameters

context	The fc2Context to be used.
channel	Channel number to use.
pChannel	Stream channel information for the specified channel.

Returns

An Error indicating the success or failure of the function.

5.16.2.3 FLYCAPTURE2_C_API fc2Error fc2GetNumStreamChannels (fc2Context context, unsigned int * numChannels)

Get the number of stream channels present on the camera.

Parameters

context	The fc2Context to be used.
numChannels	Number of stream channels present.

Returns

An Error indicating the success or failure of the function.

5.16.2.4 FLYCAPTURE2_C_API fc2Error fc2SetGigEConfig (fc2Context context, const fc2GigEConfig * pConfig)

Set the gige config specified to the camera.

Parameters

context	The fc2Context to be used.
pGigEConfig	configuration to set to camera.

Returns

An Error indicating the success or failure of the function.

5.16.2.5 FLYCAPTURE2_C_API fc2Error fc2SetGigEStreamChannelInfo (fc2Context context, unsigned int channel, fc2GigEStreamChannel * pChannel)

Set the stream channel information for the specified channel.

Note that the source UDP port of the stream channel is read-only.

Parameters

context	The fc2Context to be used.
channel	Channel number to use.
pChannel	Stream channel information to use for the specified channel.

Returns

5.17 Image Operation

The Image operations are used to retrieve images from a camera, convert between multiple pixel formats and save images to disk.

Functions

FLYCAPTURE2_C_API fc2Error fc2SetDefaultColorProcessing (fc2ColorProcessingAlgorithm default
 — Method)

Set the default color processing algorithm.

Get the default color processing algorithm.

FLYCAPTURE2 C API fc2Error fc2SetDefaultOutputFormat (fc2PixelFormat format)

Set the default output pixel format.

• FLYCAPTURE2 C API fc2Error fc2GetDefaultOutputFormat (fc2PixelFormat *pFormat)

Get the default output pixel format.

FLYCAPTURE2_C_API fc2Error fc2DetermineBitsPerPixel (fc2PixelFormat format, unsigned int *pBitsPer

 Pixel)

Calculate the bits per pixel for the specified pixel format.

FLYCAPTURE2 C API fc2Error fc2CreateImage (fc2Image *pImage)

Create a fc2Image.

• FLYCAPTURE2_C_API fc2Error fc2DestroyImage (fc2Image *image)

Destroy the fc2lmage.

• FLYCAPTURE2_C_API fc2Error fc2SetImageDimensions (fc2Image *pImage, unsigned int rows, unsigned int cols, unsigned int stride, fc2PixelFormat pixelFormat, fc2BayerTileFormat bayerFormat)

Sets the dimensions of the image object.

FLYCAPTURE2_C_API fc2Error fc2SetImageData (fc2Image *pImage, const unsigned char *pData, unsigned int dataSize)

Set the data of the Image object.

FLYCAPTURE2_C_API fc2Error fc2GetImageData (fc2Image *pImage, unsigned char **ppData)

Get a pointer to the data associated with the image.

FLYCAPTURE2 C API fc2TimeStamp fc2GetImageTimeStamp (fc2Image *pImage)

Get the timestamp data associated with the image.

FLYCAPTURE2_C_API fc2Error fc2SaveImage (fc2Image *pImage, const char *pFilename, fc2ImageFile←
 Format format)

Save the image to the specified file name with the file format specified.

FLYCAPTURE2_C_API fc2Error fc2SaveImageWithOption (fc2Image *pImage, const char *pFilename, fc2ImageFileFormat format, void *pOption)

Save the image to the specified file name with the file format specified.

- FLYCAPTURE2 C API fc2Error fc2ConvertImage (fc2Image *pImageIn, fc2Image *pImageOut)
- FLYCAPTURE2_C_API fc2Error fc2ConvertImageTo (fc2PixelFormat format, fc2Image *pImageIn, fc2Image *pImageOut)

Converts the current image buffer to the specified output format and stores the result in the specified image.

• FLYCAPTURE2_C_API fc2Error fc2CalculateImageStatistics (fc2Image *pImage, fc2ImageStatisticsContext *pImageStatisticsContext)

Calculate statistics associated with the image.

5.17 Image Operation 71

5.17.1 Detailed Description

The Image operations are used to retrieve images from a camera, convert between multiple pixel formats and save images to disk.

Operations on images are not guaranteed to be thread safe. It is recommended that operations on images be protected by thread synchronization constructs such as mutexes.

5.17.2 Function Documentation

5.17.2.1 FLYCAPTURE2_C_API fc2Error fc2CalculateImageStatistics (fc2Image * plmage, fc2ImageStatisticsContext * plmageStatisticsContext)

Calculate statistics associated with the image.

In order to collect statistics for a particular channel, the enabled flag for the channel must be set to true. Statistics can only be collected for images in Mono8, Mono16, RGB, RGBU, BGR and BGRU.

Parameters

plmage	The fc2Image to be used.
pImageStatisticsContext	The fc2ImageStatisticsContext to hold the statistics.

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.2 FLYCAPTURE2_C_API fc2Error fc2ConvertImage (fc2Image * plmageIn, fc2Image * plmageOut)

Parameters

plmageIn	
plmageOut	

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.3 FLYCAPTURE2_C_API fc2Error fc2ConvertImageTo (fc2PixelFormat format, fc2Image * plmageOut)

Converts the current image buffer to the specified output format and stores the result in the specified image.

The destination image does not need to be configured in any way before the call is made.

Parameters

format	Output format of the converted image.
plmageln	Input image.
plmageOut	Output image.

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.4 FLYCAPTURE2_C_API fc2Error fc2CreateImage (fc2Image * plmage)

Create a fc2Image.

If externally allocated memory is to be used for the converted image, simply assigning the pData member of the fc2lmage structure is insufficient. fc2SetImageData() should be called in order to populate the fc2lmage structure correctly.

See also

fc2SetImageData()

Parameters

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.5 FLYCAPTURE2_C_API fc2Error fc2DestroyImage (fc2Image * image)

Destroy the fc2Image.

Parameters

image	Pointer to image to be destroyed.
-------	-----------------------------------

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.6 FLYCAPTURE2_C_API fc2Error fc2DetermineBitsPerPixel (fc2PixelFormat format, unsigned int * pBitsPerPixel)

Calculate the bits per pixel for the specified pixel format.

5.17 Image Operation 73

Parameters

format	The pixel format.
pBitsPerPixel	The bits per pixel.

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.7 FLYCAPTURE2_C_API fc2Error fc2GetDefaultColorProcessing (fc2ColorProcessingAlgorithm * pDefaultMethod)

Get the default color processing algorithm.

Parameters

pDefaultMethod	The default color processing algorithm.
----------------	---

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.8 FLYCAPTURE2_C_API fc2Error fc2GetDefaultOutputFormat (fc2PixelFormat * pFormat)

Get the default output pixel format.

Parameters

pFormat The	e default pixel format.
-------------	-------------------------

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.9 FLYCAPTURE2 C API fc2Error fc2GetImageData (fc2Image * pImage, unsigned char ** ppData)

Get a pointer to the data associated with the image.

This function is considered unsafe. The pointer returned could be invalidated if the buffer is resized or released. The pointer may also be invalidated if the Image object is passed to fc2RetrieveBuffer().

plmage	The fc2Image to be used.
ppData	A pointer to the image data.

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.10 FLYCAPTURE2_C_API fc2TimeStamp fc2GetImageTimeStamp (fc2Image * pImage)

Get the timestamp data associated with the image.

Parameters

plmage	The fc2Image to be used.
--------	--------------------------

Returns

Timestamp data associated with the image.

5.17.2.11 FLYCAPTURE2_C_API fc2Error fc2SaveImage (fc2Image * pImage, const char * pFilename, fc2ImageFileFormat format)

Save the image to the specified file name with the file format specified.

Parameters

plmage	The fc2Image to be used.
pFilename	Filename to save image with.
format	File format to save in.

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.12 FLYCAPTURE2_C_API fc2Error fc2SaveImageWithOption (fc2Image * pImage, const char * pFilename, fc2ImageFileFormat format, void * pOption)

Save the image to the specified file name with the file format specified.

Parameters

plmage	The fc2Image to be used.
pFilename	Filename to save image with.
format	File format to save in.
pOption	Options for saving image.

Returns

5.17 Image Operation 75

5.17.2.13 FLYCAPTURE2_C_API fc2Error fc2SetDefaultColorProcessing (fc2ColorProcessingAlgorithm defaultMethod)

Set the default color processing algorithm.

This method will be used for any image with the DEFAULT algorithm set. The method used is determined at the time of the Convert() call, therefore the most recent execution of this function will take precedence. The default setting is shared within the current process.

Parameters

defaultMethod	The color processing algorithm to set.
---------------	--

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.14 FLYCAPTURE2_C_API fc2Error fc2SetDefaultOutputFormat (fc2PixelFormat format)

Set the default output pixel format.

This format will be used for any call to Convert() that does not specify an output format. The format used will be determined at the time of the Convert() call, therefore the most recent execution of this function will take precedence. The default is shared within the current process.

Parameters

format	The output pixel format to set.

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.15 FLYCAPTURE2_C_API fc2Error fc2SetImageData (fc2Image * pImage, const unsigned char * pData, unsigned int dataSize)

Set the data of the Image object.

Ownership of the image buffer is not transferred to the Image object. It is the user's responsibility to delete the buffer when it is no longer in use.

plmage	The fc2Image to be used.
pData	Pointer to the image buffer.
dataSize	Size of the image buffer.

Returns

A fc2Error indicating the success or failure of the function.

5.17.2.16 FLYCAPTURE2_C_API fc2Error fc2SetImageDimensions (fc2Image * plmage, unsigned int rows, unsigned int cols, unsigned int stride, fc2PixelFormat pixelFormat, fc2BayerTileFormat bayerFormat)

Sets the dimensions of the image object.

Parameters

plmage	The fc2lmage to be used.
rows	Number of rows to set.
cols	Number of cols to set.
stride	Stride to set.
pixelFormat	Pixel format to set.
bayerFormat	Bayer tile format to set.

Returns

5.18 Image Statistics Operation

The Image Statistics operation provides the functionality for the user to collect image channel statistics.

Functions

FLYCAPTURE2_C_API fc2Error fc2CreateImageStatistics (fc2ImageStatisticsContext *pImageStatistics
 — Context)

Create a statistics context.

 FLYCAPTURE2_C_API fc2Error fc2DestroyImageStatistics (fc2ImageStatisticsContext imageStatistics← Context)

Destroy a statistics context.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableAll (fc2ImageStatisticsContext imageStatistics← Context)

Enable all channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsDisableAll (fc2ImageStatisticsContext imageStatistics
 — Context)

Disable all channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableGreyOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the grey channel.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableRGBOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the RGB channels.

FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableHSLOnly (fc2ImageStatisticsContext image
 — StatisticsContext)

Enable only the HSL channels.

FLYCAPTURE2_C_API fc2Error fc2GetChannelStatus (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, BOOL *pEnabled)

Get the status of a statistics channel.

FLYCAPTURE2_C_API fc2Error fc2SetChannelStatus (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, BOOL enabled)

Set the status of a statistics channel.

FLYCAPTURE2_C_API fc2Error fc2GetChannelRange (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int *pMin, unsigned int *pMax)

Get the range of a statistics channel.

Get the range of a statistics channel.

FLYCAPTURE2_C_API fc2Error fc2GetChannelNumPixelValues (fc2ImageStatisticsContext image
 — StatisticsContext, fc2StatisticsChannel channel, unsigned int *pNumPixelValues)

Get the number of unique pixel values in the image.

• FLYCAPTURE2_C_API fc2Error fc2GetChannelMean (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, float *pPixelValueMean)

Get the mean of the image.

FLYCAPTURE2_C_API fc2Error fc2GetChannelHistogram (fc2ImageStatisticsContext imageStatisticsContext imageStatisticsContext

Get the histogram for the image.

FLYCAPTURE2_C_API fc2Error fc2GetImageStatistics (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int *pRangeMin, unsigned int *pRangeMax, unsigned int *pPixelValueMin, unsigned int *pPixelValueMax, unsigned int *pNumPixelValues, float *pPixelValueMean, int **ppHistogram)

Get all statistics for the image.

5.18.1 Detailed Description

The Image Statistics operation provides the functionality for the user to collect image channel statistics.

5.18.2 Function Documentation

5.18.2.1 FLYCAPTURE2_C_API fc2Error fc2CreateImageStatistics (fc2ImageStatisticsContext * pImageStatisticsContext)

Create a statistics context.

Parameters

plmageStatisticsContext	A statistics context.
-------------------------	-----------------------

Returns

A fc2Error indicating the success or failure of the function.

5.18.2.2 FLYCAPTURE2_C_API fc2Error fc2DestroyImageStatistics (fc2ImageStatisticsContext imageStatisticsContext)

Destroy a statistics context.

Parameters

imageStatisticsContext	A statistics context.

Returns

A fc2Error indicating the success or failure of the function.

5.18.2.3 FLYCAPTURE2_C_API fc2Error fc2GetChannelHistogram (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, int ** ppHistogram)

Get the histogram for the image.

imageStatisticsContext	A statistics context.
channel	The statistics channel.
ppHistogram	Pointer to an array containing the histogram.

Returns

An Error indicating the success or failure of the function.

5.18.2.4 FLYCAPTURE2_C_API fc2Error fc2GetChannelMean (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, float * pPixelValueMean)

Get the mean of the image.

Parameters

imageStatisticsContext	A statistics context.
channel	The statistics channel.
pPixelValueMean	The mean of the image.

Returns

An Error indicating the success or failure of the function.

5.18.2.5 FLYCAPTURE2_C_API fc2Error fc2GetChannelNumPixelValues (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int * pNumPixelValues)

Get the number of unique pixel values in the image.

Parameters

imageStatisticsContext	A statistics context.
channel	The statistics channel.
pNumPixelValues	The number of unique pixel values.

Returns

An Error indicating the success or failure of the function.

5.18.2.6 FLYCAPTURE2_C_API fc2Error fc2GetChannelPixelValueRange (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int * pPixelValueMin, unsigned int * pPixelValueMax)

Get the range of a statistics channel.

The values returned are the maximum values recorded for all pixels in the image.

Parameters

imageStatisticsContext	A statistics context.
channel	The statistics channel.
pPixelValueMin	The minimum pixel value.
pPixelValueMax	The maximum pixel value.

Returns

An Error indicating the success or failure of the function.

5.18.2.7 FLYCAPTURE2_C_API fc2Error fc2GetChannelRange (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int * pMin, unsigned int * pMax)

Get the range of a statistics channel.

The values returned are the maximum possible values for any given pixel in the image. This is generally 0-255 for 8 bit images, and 0-65535 for 16 bit images.

Parameters

imageStatisticsContext	A statistics context.
channel	The statistics channel.
pMin	The minimum possible value.
рМах	The maximum possible value.

Returns

An Error indicating the success or failure of the function.

5.18.2.8 FLYCAPTURE2_C_API fc2Error fc2GetChannelStatus (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, BOOL * pEnabled)

Get the status of a statistics channel.

See also

fc2SetChannelStatus()

Parameters

imageStatisticsContext	A statistics context.
channel	The statistics channel.
pEnabled	Whether the channel is enabled.

Returns

An Error indicating the success or failure of the function.

5.18.2.9 FLYCAPTURE2_C_API fc2Error fc2GetImageStatistics (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, unsigned int * pRangeMin, unsigned int * pRangeMax, unsigned int * pPixelValueMin, unsigned int * pPixelValueMax, unsigned int * pNumPixelValues, float * pPixelValueMean, int ** ppHistogram)

Get all statistics for the image.

Parameters

imageStatisticsContext	The statistics context.
channel	The statistics channel.
pRangeMin	The minimum possible value.
pRangeMax	The maximum possible value.
pPixelValueMin	The minimum pixel value.
pPixelValueMax	The maximum pixel value.
pNumPixelValues	The number of unique pixel values.
pPixelValueMean	The mean of the image.
ppHistogram	Pointer to an array containing the histogram.

Returns

A fc2Error indicating the success or failure of the function.

5.18.2.10 FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsDisableAll (fc2ImageStatisticsContext imageStatisticsContext)

Disable all channels.

Parameters

imageStatisticsContext	A statistics context.
------------------------	-----------------------

Returns

An Error indicating the success or failure of the function.

5.18.2.11 FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableAll (fc2ImageStatisticsContext imageStatisticsContext)

Enable all channels.

Parameters

imageStatisticsContext	A statistics context.

Returns

An Error indicating the success or failure of the function.

5.18.2.12 FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableGreyOnly (fc2ImageStatisticsContext imageStatisticsContext)

Enable only the grey channel.

Parameters

Returns

An Error indicating the success or failure of the function.

5.18.2.13 FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableHSLOnly (fc2ImageStatisticsContext imageStatisticsContext)

Enable only the HSL channels.

Parameters

imageStatisticsContext	A statistics context.
------------------------	-----------------------

Returns

An Error indicating the success or failure of the function.

5.18.2.14 FLYCAPTURE2_C_API fc2Error fc2ImageStatisticsEnableRGBOnly (fc2ImageStatisticsContext imageStatisticsContext)

Enable only the RGB channels.

Parameters

imageStatisticsContext	A statistics context.
magocianonocomica	7 Clationoo Contoxt.

Returns

An Error indicating the success or failure of the function.

5.18.2.15 FLYCAPTURE2_C_API fc2Error fc2SetChannelStatus (fc2ImageStatisticsContext imageStatisticsContext, fc2StatisticsChannel channel, BOOL enabled)

Set the status of a statistics channel.

See also

fc2GetChannelStatus()

Parameters

imageStatisticsContext	A statistics context.
channel	The statistics channel.
enabled	Whether the channel should be enabled.

Returns

An Error indicating the success or failure of the function.

5.19 AVI Recording Operation

The AVI recording operation provides the functionality for the user to record images to an AVI file.

Functions

• FLYCAPTURE2_C_API fc2Error fc2CreateAVI (fc2AVIContext *pAVIContext)

Create a AVI context.

FLYCAPTURE2_C_API fc2Error fc2AVIOpen (fc2AVIContext AVIContext, const char *pFileName, fc2AVI
 —
 Option *pOption)

Open an AVI file in preparation for writing Images to disk.

 FLYCAPTURE2_C_API fc2Error fc2MJPGOpen (fc2AVIContext AVIContext, const char *pFileName, fc2← MJPGOption *pOption)

Open an MJPEG file in preparation for writing Images to disk.

 FLYCAPTURE2_C_API fc2Error fc2H264Open (fc2AVIContext AVIContext, const char *pFileName, fc2← H264Option *pOption)

Open an H.264 file in preparation for writing Images to disk.

• FLYCAPTURE2_C_API fc2Error fc2AVIAppend (fc2AVIContext AVIContext, fc2Image *pImage)

Append an image to the AVI file.

FLYCAPTURE2_C_API fc2Error fc2AVIClose (fc2AVIContext AVIContext)

Close the AVI file.

FLYCAPTURE2_C_API fc2Error fc2DestroyAVI (fc2AVIContext AVIContext)

Destroy a AVI context.

5.19.1 Detailed Description

The AVI recording operation provides the functionality for the user to record images to an AVI file.

5.19.2 Function Documentation

5.19.2.1 FLYCAPTURE2_C_API fc2Error fc2AVIAppend (fc2AVIContext AVIContext, fc2Image * plmage)

Append an image to the AVI file.

Parameters

AVIContext	The AVI context to use.
plmage	The image to append.

Returns

A fc2Error indicating the success or failure of the function.

5.19.2.2 FLYCAPTURE2_C_API fc2Error fc2AVIClose (fc2AVIContext AVIContext)

Close the AVI file.

Parameters

AVIContext The AVI con	text to use.
--------------------------	--------------

Returns

A fc2Error indicating the success or failure of the function.

5.19.2.3 FLYCAPTURE2_C_API fc2Error fc2AVIOpen (fc2AVIContext AVIContext, const char * pFileName, fc2AVIOption * pOption)

Open an AVI file in preparation for writing Images to disk.

The size of AVI files is limited to 2GB. The filenames are automatically generated using the filename specified.

Parameters

AVIContext	The AVI context to use.
pFileName	The filename of the AVI file.
pOption	Options to apply to the AVI file.

Returns

A fc2Error indicating the success or failure of the function.

 $5.19.2.4 \quad \textbf{FLYCAPTURE2_C_API} \ \text{fc2Error} \ \text{fc2CreateAVI} \ (\ \text{fc2AVIContext} \ * \textit{pAVIContext} \)$

Create a AVI context.

Parameters

Returns

A fc2Error indicating the success or failure of the function.

5.19.2.5 FLYCAPTURE2_C_API fc2Error fc2DestroyAVI (fc2AVIContext AVIContext)

Destroy a AVI context.

Parameters

AVIContext | A AVI context.

Returns

A fc2Error indicating the success or failure of the function.

5.19.2.6 FLYCAPTURE2_C_API fc2Error fc2H264Open (fc2AVIContext AVIContext, const char * pFileName, fc2H264Option * pOption)

Open an H.264 file in preparation for writing Images to disk.

The size of AVI files is limited to 2GB. The filenames are automatically generated using the filename specified.

Parameters

AVIContext	The AVI context to use.
pFileName	The filename of the AVI file.
pOption	Options to apply to the AVI file.

Returns

A fc2Error indicating the success or failure of the function.

5.19.2.7 FLYCAPTURE2_C_API fc2Error fc2MJPGOpen (fc2AVIContext, const char * pFileName, fc2MJPGOption * pOption)

Open an MJPEG file in preparation for writing Images to disk.

The size of AVI files is limited to 2GB. The filenames are automatically generated using the filename specified.

Parameters

AVIContext	The AVI context to use.
pFileName	The filename of the AVI file.
pOption	Options to apply to the AVI file.

Returns

A fc2Error indicating the success or failure of the function.

5.20 TopologyNode Operation

The TopologyNode operation provides the functionality for the user to generate a tree structure of all cameras and devices connected to a computer.

Functions

FLYCAPTURE2_C_API fc2Error fc2CreateTopologyNode (fc2TopologyNodeContext *pTopologyNode ← Context)

Create a TopologyNode context.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetGuid (fc2TopologyNodeContext TopologyNode
 — Context, fc2PGRGuid *pGuid)

Get the PGRGuid associated with the node.

Get the device ID associated with the node.

Get the node type associated with the node.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetInterfaceType (fc2TopologyNodeContext Topology
 — NodeContext, fc2InterfaceType *pInterfaceType)

Get the interface type associated with the node.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetNumChildren (fc2TopologyNodeContext Topology
 — NodeContext, unsigned int *pNumChildNodes)

Get the number of child nodes.

• FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetChild (fc2TopologyNodeContext TopologyNodeContext TopologyNodeContext)

Context, unsigned int position, fc2TopologyNodeContext *pChildTopologyNodeContext)

Get child node located at the specified position.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeAddChild (fc2TopologyNodeContext TopologyNodeContext TopologyNodeContext)

Add the specified TopologyNode as a child of the node.

Get the number of ports.

FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetPortType (fc2TopologyNodeContext TopologyNode
 — Context, unsigned int position, fc2PortType *pPortType)

Get type of port located at the specified position.

Add the specified PortType as a port of the node.

FLYCAPTURE2_C_API BOOL fc2TopologyNodeAssignGuidToNode (fc2TopologyNodeContext Topology
 — NodeContext, fc2PGRGuid guid, int deviceId)

Assign a PGRGuid and device ID to the node.

FLYCAPTURE2_C_API BOOL fc2TopologyNodeAssignGuidToNodeEx (fc2TopologyNodeContext Topology
 — NodeContext, fc2PGRGuid guid, int deviceId, fc2NodeType nodeType)

Assign a PGRGuid, device ID and nodeType to the node.

FLYCAPTURE2_C_API fc2Error fc2DestroyTopologyNode (fc2TopologyNodeContext TopologyNodeContext)
 Destroy a TopologyNode context.

5.20.1 Detailed Description

The TopologyNode operation provides the functionality for the user to generate a tree structure of all cameras and devices connected to a computer.

5.20.2 Function Documentation

5.20.2.1 FLYCAPTURE2_C_API fc2Error fc2CreateTopologyNode (fc2TopologyNodeContext * pTopologyNodeContext)

Create a TopologyNode context.

Parameters

pTopologyNodeContext

Returns

A fc2Error indicating the success or failure of the function.

Destroy a TopologyNode context.

Parameters

TopologyNodeContext	A Topology Node context.
---------------------	--------------------------

Returns

A fc2Error indicating the success or failure of the function.

Add the specified TopologyNode as a child of the node.

Parameters

TopologyNodeContext	The Topology Node context to use.
TopologyNodeChildContext	The TopologyNode child context to add.

Returns

A fc2Error indicating the success or failure of the function.

Add the specified PortType as a port of the node.

Parameters

TopologyNodeContext	The Topology Node context to use.
portType	childPort The port to add.

Returns

A fc2Error indicating the success or failure of the function.

Assign a PGRGuid and device ID to the node.

Parameters

TopologyNodeContext	The Topology Node context to use.
guid	PGRGuid to be assigned.
deviceld	Device ID to be assigned.

Returns

A fc2Error indicating the success or failure of the function.

Assign a PGRGuid, device ID and nodeType to the node.

Parameters

TopologyNodeContext	The Topology Node context to use.
guid	PGRGuid to be assigned.
deviceId	Device ID to be assigned.
nodeType	NodeType to be assigned

Returns

A fc2Error indicating the success or failure of the function.

5.20.2.7 FLYCAPTURE2_C_API fc2Error fc2TopologyNodeGetChild (fc2TopologyNodeContext
TopologyNodeContext, unsigned int position, fc2TopologyNodeContext * pChildTopologyNodeContext)

Get child node located at the specified position.

Parameters

TopologyNodeContext	The Topology Node context to use.
position	Position of the child node.
pChildTopologyNodeContext	The Topology Node context the contains information on the child topology

Returns

A fc2Error indicating the success or failure of the function.

Get the device ID associated with the node.

Parameters

TopologyNodeContext	The Topology Node context to use.
ρID	Device ID of the node.

Returns

A fc2Error indicating the success or failure of the function.

Get the PGRGuid associated with the node.

Parameters

TopologyNodeContext	The Topology Node context to use.
pGuid	The unique identifier associated with the node.

Returns

A fc2Error indicating the success or failure of the function.

Get the interface type associated with the node.

Parameters

TopologyNodeContext	The Topology Node context to use.
pInterfaceType	Interface type of the node.

Returns

A fc2Error indicating the success or failure of the function.

Get the node type associated with the node.

Parameters

TopologyNodeContext	The Topology Node context to use.
pNodeType	Node type of the node.

Returns

A fc2Error indicating the success or failure of the function.

Get the number of child nodes.

Parameters

TopologyNodeContext	The Topology Node context to use.
pNumChildNodes	Number of child nodes.

Returns

A fc2Error indicating the success or failure of the function.

Get the number of ports.

Parameters

TopologyNodeContext	The Topology Node context to use.
pNumPorts	Number of ports.

Returns

A fc2Error indicating the success or failure of the function.

Get type of port located at the specified position.

Parameters

TopologyNodeContext	The Topology Node context to use.
position	Position of the port.
pPortType	PortType at the specified position.

Returns

A fc2Error indicating the success or failure of the function.

5.21 Utilities 93

5.21 Utilities

The utility operations are used to query for general system information such as operating system, available memory etc.

Functions

• FLYCAPTURE2 C API fc2Error fc2CheckDriver (const fc2PGRGuid *pGuid)

Check for driver compatibility for the given camera guid.

Get the driver's name for a device.

• FLYCAPTURE2_C_API fc2Error fc2GetSystemInfo (fc2SystemInfo *pSystemInfo)

Get system information.

FLYCAPTURE2_C_API fc2Error fc2GetLibraryVersion (fc2Version *pVersion)

Get library version.

• FLYCAPTURE2_C_API fc2Error fc2LaunchBrowser (const char *pAddress)

Launch a URL in the system default browser.

• FLYCAPTURE2_C_API fc2Error fc2LaunchHelp (const char *pFileName)

Open a CHM file in the system default CHM viewer.

• FLYCAPTURE2_C_API fc2Error fc2LaunchCommand (const char *pCommand)

Execute a command in the terminal.

FLYCAPTURE2_C_API fc2Error fc2LaunchCommandAsync (const char *pCommand, fc2AsyncCommand
 — Callback pCallback, void *pUserData)

Execute a command in the terminal.

• FLYCAPTURE2_C_API const char * fc2ErrorToDescription (fc2Error error)

Get a string representation of an error.

5.21.1 Detailed Description

The utility operations are used to query for general system information such as operating system, available memory etc.

It can also be used to launch browsers, CHM viewers or terminal commands.

5.21.2 Function Documentation

5.21.2.1 FLYCAPTURE2_C_API fc2Error fc2CheckDriver (const fc2PGRGuid * pGuid)

Check for driver compatibility for the given camera guid.

Parameters

pGuid The PGRGuid of the device to check.

Returns

FC2_ERROR_OK if the library is compatible with the currently loaded driver, otherwise an error indicating the type of failure.

5.21.2.2 FLYCAPTURE2_C_API const char* fc2ErrorToDescription (fc2Error error)

Get a string representation of an error.

Parameters

error Error to	be parsed.
----------------	------------

Returns

A fc2Error indicating the success or failure of the function.

5.21.2.3 FLYCAPTURE2_C_API fc2Error fc2GetDriverDeviceName (const fc2PGRGuid * pGuid, char * pDeviceName, size_t * deviceNameLength)

Get the driver's name for a device.

Parameters

pGuid	The PGRGuid of the device to check.
pDeviceName	The device name will be returned in this string
pDeviceNameLength	The length of the device name string returned

Returns

An Error indicating the success or failure of the function.

5.21.2.4 FLYCAPTURE2_C_API fc2Error fc2GetLibraryVersion (fc2Version * pVersion)

Get library version.

Parameters

1	n\/orcion	Structure to receive the library version.
	pversion	Structure to receive the library version.

Returns

A fc2Error indicating the success or failure of the function.

5.21 Utilities 95

 $5.21.2.5 \quad \textbf{FLYCAPTURE2_C_API fc2Error fc2GetSystemInfo} \; (\; \textbf{fc2SystemInfo} \;) \\$

Get system information.

Parameters

<i>pSystemInfo</i> Structure to receive system information.

Returns

A fc2Error indicating the success or failure of the function.

5.21.2.6 FLYCAPTURE2 C API fc2Error fc2LaunchBrowser (const char * pAddress)

Launch a URL in the system default browser.

Parameters

pAddress	URL to open in browser.
----------	-------------------------

Returns

A fc2Error indicating the success or failure of the function.

5.21.2.7 FLYCAPTURE2_C_API fc2Error fc2LaunchCommand (const char * pCommand)

Execute a command in the terminal.

This is a blocking call that will return when the command completes.

Parameters

pCommand	Command to execute.

Returns

A fc2Error indicating the success or failure of the function.

5.21.2.8 FLYCAPTURE2_C_API fc2Error fc2LaunchCommandAsync (const char * pCommand, fc2AsyncCommandCallback pCallback, void * pUserData)

Execute a command in the terminal.

This is a non-blocking call that will return immediately. The return value of the command can be retrieved in the callback.

Parameters

pCommand	Command to execute.
pCallback	Callback to fire when command is complete.
pUserData	Data pointer to pass to callback.

5.21 Utilities 97

Returns

A fc2Error indicating the success or failure of the function.

5.21.2.9 FLYCAPTURE2_C_API fc2Error fc2LaunchHelp (const char * pFileName)

Open a CHM file in the system default CHM viewer.

Parameters

pFileName	Filename of CHM file to open.
-----------	-------------------------------

Returns

A fc2Error indicating the success or failure of the function.

5.22 TypeDefs

Data Structures

struct fc2PGRGuid

A GUID to the camera.

Macros

- #define FALSE 0
- #define TRUE 1
- #define FULL_32BIT_VALUE 0x7FFFFFF
- #define MAX_STRING_LENGTH 512

Typedefs

- · typedef int BOOL
- typedef void * fc2Context

A context to the FlyCapture2 C library.

typedef void * fc2GuiContext

A context to the FlyCapture2 C GUI library.

typedef void * fc2lmagelmpl

An internal pointer used in the fc2Image structure.

typedef void * fc2AVIContext

A context referring to the AVI recorder object.

typedef void * fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

typedef void * fc2TopologyNodeContext

A context referring to the TopologyNode object.

- 5.22.1 Detailed Description
- 5.22.2 Macro Definition Documentation
- 5.22.2.1 #define FALSE 0
- 5.22.2.2 #define FULL_32BIT_VALUE 0x7FFFFFF
- 5.22.2.3 #define MAX_STRING_LENGTH 512
- 5.22.2.4 #define TRUE 1
- 5.22.3 Typedef Documentation
- 5.22.3.1 typedef int BOOL
- 5.22.3.2 typedef void* fc2AVIContext

A context referring to the AVI recorder object.

5.22 TypeDefs 99

5.22.3.3 typedef void* fc2Context

A context to the FlyCapture2 C library.

It must be created before performing any calls to the library.

5.22.3.4 typedef void* fc2GuiContext

A context to the FlyCapture2 C GUI library.

It must be created before performing any calls to the library.

5.22.3.5 typedef void* fc2ImageImpl

An internal pointer used in the fc2Image structure.

5.22.3.6 typedef void* fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

5.22.3.7 typedef void* fc2TopologyNodeContext

A context referring to the TopologyNode object.

5.23 Enumerations

Enumerations

```
enum fc2Error {
 FC2 ERROR UNDEFINED = -1,
 FC2 ERROR OK,
 FC2 ERROR FAILED,
 FC2 ERROR NOT IMPLEMENTED,
 FC2_ERROR_FAILED_BUS_MASTER_CONNECTION,
 FC2_ERROR_NOT_CONNECTED,
 FC2 ERROR INIT FAILED,
 FC2 ERROR NOT INTITIALIZED,
 FC2_ERROR_INVALID_PARAMETER,
 FC2_ERROR_INVALID_SETTINGS,
 FC2 ERROR INVALID BUS MANAGER,
 FC2 ERROR MEMORY ALLOCATION FAILED,
 FC2 ERROR LOW LEVEL FAILURE,
 FC2 ERROR NOT FOUND,
 FC2 ERROR FAILED GUID.
 FC2_ERROR_INVALID_PACKET_SIZE,
 FC2_ERROR_INVALID_MODE,
 FC2_ERROR_NOT_IN_FORMAT7,
 FC2_ERROR_NOT_SUPPORTED,
 FC2_ERROR_TIMEOUT,
 FC2_ERROR_BUS_MASTER_FAILED,
 FC2 ERROR INVALID GENERATION,
 FC2 ERROR LUT_FAILED,
 FC2 ERROR IIDC FAILED,
 FC2 ERROR STROBE FAILED,
 FC2 ERROR TRIGGER FAILED,
 FC2 ERROR PROPERTY FAILED,
 FC2_ERROR_PROPERTY_NOT_PRESENT,
 FC2 ERROR REGISTER FAILED,
 FC2 ERROR READ REGISTER FAILED,
 FC2_ERROR_WRITE_REGISTER_FAILED,
 FC2 ERROR ISOCH FAILED,
 FC2 ERROR ISOCH ALREADY STARTED,
 FC2 ERROR ISOCH NOT STARTED,
 FC2_ERROR_ISOCH_START_FAILED,
 FC2_ERROR_ISOCH_RETRIEVE_BUFFER_FAILED,
 FC2_ERROR_ISOCH_STOP_FAILED,
 FC2 ERROR ISOCH SYNC FAILED,
 FC2_ERROR_ISOCH_BANDWIDTH_EXCEEDED,
 FC2_ERROR_IMAGE_CONVERSION_FAILED,
 FC2_ERROR_IMAGE_LIBRARY_FAILURE,
 FC2_ERROR_BUFFER_TOO SMALL,
 FC2 ERROR IMAGE CONSISTENCY ERROR,
 FC2 ERROR INCOMPATIBLE DRIVER,
 FC2 ERROR FORCE 32BITS = FULL 32BIT VALUE }
    The error types returned by functions.

    enum fc2BusCallbackType {

 FC2 BUS RESET,
 FC2 ARRIVAL,
 FC2 REMOVAL
 FC2 CALLBACK TYPE FORCE 32BITS = FULL 32BIT VALUE }
    The type of bus callback to register a callback function for.
```

Generated by Doxygen

5.23 Enumerations 101

```
    enum fc2GrabMode {

 FC2_DROP_FRAMES,
 FC2_BUFFER_FRAMES,
 FC2_UNSPECIFIED_GRAB_MODE,
 FC2_GRAB_MODE_FORCE_32BITS = FULL_32BIT_VALUE }
    The grab strategy employed during image transfer.

    enum fc2GrabTimeout {

 FC2 TIMEOUT NONE = 0,
 FC2 TIMEOUT INFINITE = -1,
 FC2_TIMEOUT_UNSPECIFIED = -2,
 FC2_GRAB_TIMEOUT_FORCE_32BITS = FULL_32BIT_VALUE }
    Timeout options for grabbing images.

    enum fc2BandwidthAllocation {

 FC2_BANDWIDTH_ALLOCATION_OFF = 0,
 FC2_BANDWIDTH_ALLOCATION_ON = 1,
 FC2_BANDWIDTH_ALLOCATION_UNSUPPORTED = 2,
 FC2_BANDWIDTH_ALLOCATION_UNSPECIFIED = 3,
 FC2_BANDWIDTH_ALLOCATION_FORCE_32BITS = FULL_32BIT_VALUE }
    Bandwidth allocation options for 1394 devices.
enum fc2InterfaceType {
 FC2 INTERFACE IEEE1394,
 FC2 INTERFACE USB 2,
 FC2_INTERFACE_USB_3,
 FC2 INTERFACE_GIGE,
 FC2_INTERFACE_UNKNOWN,
 FC2_INTERFACE_TYPE_FORCE_32BITS = FULL_32BIT_VALUE }
    Interfaces that a camera may use to communicate with a host.
enum fc2PropertyType {
 FC2_BRIGHTNESS,
 FC2 AUTO EXPOSURE,
 FC2_SHARPNESS,
 FC2_WHITE_BALANCE,
 FC2 HUE,
 FC2 SATURATION,
 FC2_GAMMA,
 FC2 IRIS,
 FC2 FOCUS,
 FC2 ZOOM,
 FC2_PAN,
 FC2_TILT,
 FC2_SHUTTER,
 FC2_GAIN,
 FC2_TRIGGER_MODE,
 FC2_TRIGGER_DELAY,
 FC2 FRAME RATE,
 FC2 TEMPERATURE,
 FC2_UNSPECIFIED_PROPERTY_TYPE,
 FC2_PROPERTY_TYPE_FORCE_32BITS = FULL_32BIT_VALUE }
    Camera properties.

    enum fc2FrameRate {
```

```
FC2_FRAMERATE_1_875,
FC2_FRAMERATE_3_75,
FC2_FRAMERATE_7_5,
FC2_FRAMERATE_15,
FC2_FRAMERATE_30,
FC2_FRAMERATE_60,
FC2_FRAMERATE_120,
FC2_FRAMERATE_240,
FC2_FRAMERATE_240,
FC2_FRAMERATE_FORMAT7,
FC2_NUM_FRAMERATES,
FC2_FRAMERATE_FORCE_32BITS = FULL_32BIT_VALUE }
```

Frame rates in frames per second.

```
enum fc2VideoMode {
 FC2 VIDEOMODE 160x120YUV444,
 FC2 VIDEOMODE 320x240YUV422,
 FC2_VIDEOMODE_640x480YUV411,
 FC2_VIDEOMODE_640x480YUV422,
 FC2 VIDEOMODE 640x480RGB,
 FC2_VIDEOMODE_640x480Y8,
 FC2_VIDEOMODE_640x480Y16,
 FC2_VIDEOMODE_800x600YUV422,
 FC2 VIDEOMODE 800x600RGB,
 FC2 VIDEOMODE 800x600Y8,
 FC2_VIDEOMODE_800x600Y16,
 FC2_VIDEOMODE_1024x768YUV422,
 FC2_VIDEOMODE_1024x768RGB,
 FC2_VIDEOMODE_1024x768Y8,
 FC2_VIDEOMODE_1024x768Y16,
 FC2_VIDEOMODE_1280x960YUV422,
 FC2 VIDEOMODE 1280x960RGB,
 FC2 VIDEOMODE 1280x960Y8,
 FC2_VIDEOMODE_1280x960Y16,
 FC2 VIDEOMODE 1600x1200YUV422,
 FC2_VIDEOMODE_1600x1200RGB,
 FC2_VIDEOMODE_1600x1200Y8,
 FC2_VIDEOMODE_1600x1200Y16,
 FC2 VIDEOMODE FORMAT7,
 FC2 NUM VIDEOMODES,
 FC2_VIDEOMODE_FORCE_32BITS = FULL_32BIT_VALUE }
```

DCAM video modes.

enum fc2Mode {

5.23 Enumerations 103

```
FC2\_MODE\_0 = 0,
 FC2 MODE 1,
 FC2 MODE 2,
 FC2_MODE_3,
 FC2_MODE_4,
 FC2 MODE 5,
 FC2 MODE_6,
 FC2 MODE 7,
 FC2 MODE 8,
 FC2 MODE 9,
 FC2_MODE_10,
 FC2_MODE_11,
 FC2_MODE_12,
 FC2 MODE 13,
 FC2_MODE_14,
 FC2_MODE_15,
 FC2 MODE 16,
 FC2_MODE_17,
 FC2_MODE_18,
 FC2 MODE 19,
 FC2 MODE 20,
 FC2 MODE 21,
 FC2_MODE_22,
 FC2_MODE_23,
 FC2 MODE 24,
 FC2_MODE_25,
 FC2_MODE_26,
 FC2 MODE 27,
 FC2 MODE 28.
 FC2 MODE_29,
 FC2_MODE_30,
 FC2_MODE_31,
 FC2 NUM MODES,
 FC2_MODE_FORCE_32BITS = FULL_32BIT_VALUE }
    Camera modes for DCAM formats as well as Format7.
enum fc2PixelFormat {
 FC2_PIXEL_FORMAT_MONO8 = 0x80000000,
 FC2_PIXEL_FORMAT_411YUV8 = 0x40000000,
 FC2_PIXEL_FORMAT_422YUV8 = 0x200000000,
 FC2 PIXEL FORMAT 444YUV8 = 0x10000000,
 FC2 PIXEL FORMAT RGB8 = 0x08000000,
 FC2 PIXEL FORMAT MONO16 = 0x04000000,
 FC2 PIXEL FORMAT RGB16 = 0x02000000,
 FC2_PIXEL_FORMAT_S_MONO16 = 0x01000000,
 FC2_PIXEL_FORMAT_S_RGB16 = 0x00800000,
 FC2_PIXEL_FORMAT_RAW8 = 0x00400000,
 FC2_PIXEL_FORMAT_RAW16 = 0x00200000,
 FC2 PIXEL FORMAT MONO12 = 0 \times 00100000,
 FC2_PIXEL_FORMAT_RAW12 = 0x00080000,
 FC2_PIXEL_FORMAT_BGR = 0x80000008,
 FC2 PIXEL FORMAT BGRU = 0x40000008,
 FC2 PIXEL FORMAT RGB = FC2 PIXEL FORMAT RGB8,
 FC2_PIXEL_FORMAT_RGBU = 0x40000002,
 FC2 PIXEL FORMAT BGR16 = 0x02000001,
 FC2 PIXEL FORMAT BGRU16 = 0x02000002,
 FC2 PIXEL FORMAT 422YUV8 JPEG = 0x40000001,
 FC2_NUM_PIXEL_FORMATS = 20,
 FC2_UNSPECIFIED_PIXEL_FORMAT = 0 }
```

```
Pixel formats available for Format7 modes.
enum fc2BusSpeed {
 FC2 BUSSPEED S100,
 FC2_BUSSPEED_S200,
 FC2_BUSSPEED_S400,
 FC2 BUSSPEED S480,
 FC2_BUSSPEED_S800,
 FC2_BUSSPEED_S1600,
 FC2 BUSSPEED S3200,
 FC2 BUSSPEED S5000,
 FC2_BUSSPEED_10BASE_T,
 FC2_BUSSPEED_100BASE_T,
 FC2 BUSSPEED 1000BASE T,
 FC2 BUSSPEED 10000BASE T,
 FC2_BUSSPEED_S_FASTEST,
 FC2_BUSSPEED_ANY,
 FC2 BUSSPEED SPEED UNKNOWN = -1,
 FC2 BUSSPEED FORCE 32BITS = FULL 32BIT VALUE }
    Bus speeds.

    enum fc2PCleBusSpeed {

 FC2 PCIE BUSSPEED 2 5,
 FC2_PCIE_BUSSPEED_5_0,
 FC2_PCIE_BUSSPEED_UNKNOWN = -1,
 FC2_PCIE_BUSSPEED_FORCE_32BITS = FULL_32BIT_VALUE }
enum fc2DriverType {
 FC2_DRIVER_1394_CAM,
 FC2_DRIVER_1394_PRO,
 FC2 DRIVER 1394 JUJU,
 FC2_DRIVER_1394_VIDEO1394,
 FC2_DRIVER_1394_RAW1394,
 FC2 DRIVER USB NONE,
 FC2 DRIVER USB CAM,
 FC2 DRIVER USB3 PRO,
 FC2_DRIVER_GIGE_NONE,
 FC2 DRIVER GIGE FILTER,
 FC2 DRIVER_GIGE_PRO,
 FC2 DRIVER GIGE LWF,
 FC2 DRIVER UNKNOWN = -1,
 FC2 DRIVER FORCE 32BITS = FULL 32BIT VALUE }
    Types of low level drivers that FlyCapture uses.
• enum fc2ColorProcessingAlgorithm {
 FC2_DEFAULT,
 FC2 NO COLOR PROCESSING,
 FC2 NEAREST NEIGHBOR FAST.
 FC2 EDGE SENSING,
 FC2 HQ LINEAR,
 FC2 RIGOROUS,
 FC2 IPP,
 FC2 DIRECTIONAL,
 FC2_COLOR_PROCESSING_ALGORITHM_FORCE_32BITS = FULL_32BIT_VALUE }
    Color processing algorithms.

    enum fc2BayerTileFormat {

 FC2 BT NONE,
 FC2 BT RGGB,
 FC2 BT GRBG,
 FC2 BT GBRG,
 FC2 BT BGGR,
 FC2_BT_FORCE_32BITS = FULL_32BIT_VALUE }
```

5.23 Enumerations 105

Bayer tile formats.

```
    enum fc2ImageFileFormat {
        FC2_FROM_FILE_EXT = -1,
        FC2_PGM,
        FC2_PPM,
        FC2_BMP,
        FC2_JPEG,
        FC2_JPEG2000,
        FC2_TIFF,
        FC2_PNG,
        FC2_RAW,
        FC2_IMAGE_FILE_FORMAT_FORCE_32BITS = FULL_32BIT_VALUE }
```

File formats to be used for saving images to disk.

5.23.1 Detailed Description

5.23.2 Enumeration Type Documentation

5.23.2.1 enum fc2BandwidthAllocation

Bandwidth allocation options for 1394 devices.

Enumerator

FC2_BANDWIDTH_ALLOCATION_OFF Do not allocate bandwidth.

FC2_BANDWIDTH_ALLOCATION_ON Allocate bandwidth. This is the default setting.

FC2_BANDWIDTH_ALLOCATION_UNSUPPORTED Bandwidth allocation is not supported by either the camera or operating system.

FC2_BANDWIDTH_ALLOCATION_UNSPECIFIED Not specified. This leaves the current setting unchanged.

FC2_BANDWIDTH_ALLOCATION_FORCE_32BITS

5.23.2.2 enum fc2BayerTileFormat

Bayer tile formats.

```
FC2_BT_NONE No bayer tile format.
FC2_BT_RGGB Red-Green-Green-Blue.
FC2_BT_GRBG Green-Red-Blue-Green.
FC2_BT_GBRG Green-Blue-Red-Green.
FC2_BT_BGGR Blue-Green-Green-Red.
FC2_BT_FORCE_32BITS
```

5.23.2.3 enum fc2BusCallbackType

The type of bus callback to register a callback function for.

Enumerator

```
FC2_BUS_RESET Register for all bus events.FC2_ARRIVAL Register for arrivals only.FC2_REMOVAL Register for removals only.
```

FC2_CALLBACK_TYPE_FORCE_32BITS

5.23.2.4 enum fc2BusSpeed

Bus speeds.

Enumerator

```
FC2_BUSSPEED_S100 100Mbits/sec.
FC2_BUSSPEED_S200 200Mbits/sec.
FC2 BUSSPEED S400 400Mbits/sec.
FC2 BUSSPEED $480 480Mbits/sec. Only for USB2 cameras.
FC2 BUSSPEED S800 800Mbits/sec.
FC2 BUSSPEED S1600 1600Mbits/sec.
FC2_BUSSPEED_S3200 3200Mbits/sec.
FC2_BUSSPEED_S5000 5000Mbits/sec. Only for USB3 cameras.
FC2_BUSSPEED_10BASE_T 10Base-T. Only for GigE cameras.
FC2_BUSSPEED_100BASE_T 100Base-T. Only for GigE cameras.
FC2_BUSSPEED_1000BASE_T 1000Base-T (Gigabit Ethernet). Only for GigE cameras.
FC2 BUSSPEED 10000BASE T 10000Base-T. Only for GigE cameras.
FC2_BUSSPEED_S_FASTEST The fastest speed available.
FC2_BUSSPEED_ANY Any speed that is available.
FC2_BUSSPEED_SPEED_UNKNOWN Unknown bus speed.
FC2_BUSSPEED_FORCE_32BITS
```

5.23.2.5 enum fc2ColorProcessingAlgorithm

FC2 DEFAULT Default method.

Color processing algorithms.

Please refer to our knowledge base at article at http://www.ptgrey.com/support/kb/index. \leftarrow asp?a=4&q=33 for complete details for each algorithm.

Enumerator

```
FC2_NO_COLOR_PROCESSING No color processing.
```

FC2_NEAREST_NEIGHBOR_FAST Fastest but lowest quality. Equivalent to FLYCAPTURE_NEAREST

NEIGHBOR FAST in FlyCapture.

FC2_EDGE_SENSING Weights surrounding pixels based on localized edge orientation.

FC2_HQ_LINEAR Well-balanced speed and quality.

FC2_RIGOROUS Slowest but produces good results.

FC2_IPP Multithreaded with similar results to edge sensing.

FC2_DIRECTIONAL Best quality but much faster than rigorous.

FC2_COLOR_PROCESSING_ALGORITHM_FORCE_32BITS

5.23 Enumerations 107

5.23.2.6 enum fc2DriverType

Types of low level drivers that FlyCapture uses.

Enumerator

FC2_DRIVER_1394_CAM PGRCam.sys.

FC2_DRIVER_1394_PRO PGR1394.sys.

FC2_DRIVER_1394_JUJU firewire core.

FC2_DRIVER_1394_VIDEO1394 video1394.

FC2 DRIVER 1394 RAW1394 raw1394.

FC2_DRIVER_USB_NONE No usb driver used just BSD stack. (Linux only)

FC2 DRIVER USB CAM PGRUsbCam.sys.

FC2_DRIVER_USB3_PRO PGRXHCI.sys.

FC2_DRIVER_GIGE_NONE no GigE drivers used, MS/BSD stack.

FC2_DRIVER_GIGE_FILTER PGRGigE.sys.

FC2_DRIVER_GIGE_PRO PGRGigEPro.sys.

FC2_DRIVER_GIGE_LWF PgrLwf.sys.

FC2_DRIVER_UNKNOWN Unknown driver type.

FC2 DRIVER FORCE 32BITS

5.23.2.7 enum fc2Error

The error types returned by functions.

Enumerator

FC2_ERROR_UNDEFINED Undefined.

FC2_ERROR_OK Function returned with no errors.

FC2_ERROR_FAILED General failure.

FC2 ERROR NOT IMPLEMENTED Function has not been implemented.

FC2_ERROR_FAILED_BUS_MASTER_CONNECTION Could not connect to Bus Master.

FC2_ERROR_NOT_CONNECTED Camera has not been connected.

FC2_ERROR_INIT_FAILED Initialization failed.

FC2_ERROR_NOT_INTITIALIZED Camera has not been initialized.

FC2_ERROR_INVALID_PARAMETER Invalid parameter passed to function.

FC2_ERROR_INVALID_SETTINGS Setting set to camera is invalid.

FC2_ERROR_INVALID_BUS_MANAGER Invalid Bus Manager object.

FC2_ERROR_MEMORY_ALLOCATION_FAILED Could not allocate memory.

FC2_ERROR_LOW_LEVEL_FAILURE Low level error.

FC2_ERROR_NOT_FOUND Device not found.

FC2_ERROR_FAILED_GUID GUID failure.

FC2 ERROR INVALID PACKET SIZE Packet size set to camera is invalid.

FC2_ERROR_INVALID_MODE Invalid mode has been passed to function.

FC2_ERROR_NOT_IN_FORMAT7 Error due to not being in Format7.

FC2_ERROR_NOT_SUPPORTED This feature is unsupported.

- FC2 ERROR TIMEOUT Timeout error.
- FC2_ERROR_BUS_MASTER_FAILED Bus Master Failure.
- FC2_ERROR_INVALID_GENERATION Generation Count Mismatch.
- FC2_ERROR_LUT_FAILED Look Up Table failure.
- FC2 ERROR IIDC FAILED IIDC failure.
- FC2_ERROR_STROBE_FAILED Strobe failure.
- FC2_ERROR_TRIGGER_FAILED Trigger failure.
- FC2 ERROR PROPERTY FAILED Property failure.
- FC2 ERROR PROPERTY_NOT_PRESENT Property is not present.
- FC2_ERROR_REGISTER_FAILED Register access failed.
- FC2_ERROR_READ_REGISTER_FAILED Register read failed.
- FC2_ERROR_WRITE_REGISTER_FAILED Register write failed.
- FC2 ERROR ISOCH FAILED Isochronous failure.
- FC2_ERROR_ISOCH_ALREADY_STARTED Isochronous transfer has already been started.
- FC2_ERROR_ISOCH_NOT_STARTED Isochronous transfer has not been started.
- FC2 ERROR ISOCH START FAILED Isochronous start failed.
- FC2_ERROR_ISOCH_RETRIEVE_BUFFER_FAILED Isochronous retrieve buffer failed.
- FC2_ERROR_ISOCH_STOP_FAILED Isochronous stop failed.
- FC2_ERROR_ISOCH_SYNC_FAILED Isochronous image synchronization failed.
- FC2_ERROR_ISOCH_BANDWIDTH_EXCEEDED Isochronous bandwidth exceeded.
- FC2_ERROR_IMAGE_CONVERSION_FAILED Image conversion failed.
- FC2_ERROR_IMAGE_LIBRARY_FAILURE Image library failure.
- FC2_ERROR_BUFFER_TOO_SMALL Buffer is too small.
- FC2_ERROR_IMAGE_CONSISTENCY_ERROR There is an image consistency error.
- FC2_ERROR_INCOMPATIBLE_DRIVER The installed driver is not compatible with the library.
- FC2 ERROR FORCE 32BITS

5.23.2.8 enum fc2FrameRate

Frame rates in frames per second.

- **FC2_FRAMERATE_1_875** 1.875 fps.
- FC2_FRAMERATE_3_75 3.75 fps.
- FC2_FRAMERATE_7_5 7.5 fps.
- FC2_FRAMERATE_15 15 fps.
- FC2_FRAMERATE_30 30 fps.
- FC2_FRAMERATE_60 60 fps.
- FC2_FRAMERATE_120 120 fps.
- FC2_FRAMERATE_240 240 fps.
- FC2_FRAMERATE_FORMAT7 Custom frame rate for Format7 functionality.
- FC2_NUM_FRAMERATES Number of possible camera frame rates.
- FC2_FRAMERATE_FORCE_32BITS

5.23 Enumerations 109

5.23.2.9 enum fc2GrabMode

The grab strategy employed during image transfer.

This type controls how images that stream off the camera accumulate in a user buffer for handling.

Enumerator

FC2_DROP_FRAMES Grabs the newest image in the user buffer each time the RetrieveBuffer() function is called. Older images are dropped instead of accumulating in the user buffer. Grabbing blocks if the camera has not finished transmitting the next available image. If the camera is transmitting images faster than the application can grab them, images may be dropped and only the most recent image is stored for grabbing. Note that this mode is the equivalent of flycaptureLockLatest in earlier versions of the FlyCapture SDK.

FC2_BUFFER_FRAMES Images accumulate in the user buffer, and the oldest image is grabbed for handling before being discarded. This member can be used to guarantee that each image is seen. However, image processing time must not exceed transmission time from the camera to the buffer. Grabbing blocks if the camera has not finished transmitting the next available image. The buffer size is controlled by the numBuffers parameter in the FC2Config struct. Note that this mode is the equivalent of flycaptureLock Next in earlier versions of the FlyCapture SDK.

FC2_UNSPECIFIED_GRAB_MODE Unspecified grab mode.

FC2_GRAB_MODE_FORCE_32BITS

5.23.2.10 enum fc2GrabTimeout

Timeout options for grabbing images.

Enumerator

FC2_TIMEOUT_NONE Non-blocking wait.
FC2_TIMEOUT_INFINITE Wait indefinitely.
FC2_TIMEOUT_UNSPECIFIED Unspecified timeout setting.
FC2_GRAB_TIMEOUT_FORCE_32BITS

5.23.2.11 enum fc2ImageFileFormat

File formats to be used for saving images to disk.

```
FC2_FROM_FILE_EXT Determine file format from file extension.
FC2_PGM Portable gray map.
FC2_PPM Portable pixmap.
FC2_BMP Bitmap.
FC2_JPEG JPEG.
FC2_JPEG2000 JPEG 2000.
FC2_TIFF Tagged image file format.
FC2_PNG Portable network graphics.
FC2_RAW Raw data.
FC2_IMAGE_FILE_FORMAT_FORCE_32BITS
```

5.23.2.12 enum fc2InterfaceType

Interfaces that a camera may use to communicate with a host.

Enumerator

```
FC2_INTERFACE_IEEE1394 | IEEE-1394 (Includes 1394a and 1394b).
FC2_INTERFACE_USB_2  USB 2.0.
FC2_INTERFACE_USB_3  USB 3.0.
FC2_INTERFACE_GIGE  GigE.
FC2_INTERFACE_UNKNOWN  Unknown interface.
FC2_INTERFACE_TYPE_FORCE_32BITS
```

5.23.2.13 enum fc2Mode

Camera modes for DCAM formats as well as Format7.

```
FC2_MODE_0
FC2_MODE_1
FC2_MODE_2
FC2_MODE_3
FC2_MODE_4
FC2_MODE_5
FC2_MODE_6
FC2_MODE_7
FC2 MODE 8
FC2_MODE_9
FC2_MODE_10
FC2 MODE 11
FC2_MODE_12
FC2 MODE 13
FC2_MODE_14
FC2 MODE 15
FC2 MODE 16
FC2_MODE_17
FC2_MODE_18
FC2_MODE_19
FC2_MODE_20
FC2_MODE_21
FC2_MODE_22
FC2_MODE_23
FC2_MODE_24
FC2_MODE_25
FC2_MODE_26
FC2_MODE_27
FC2_MODE_28
FC2 MODE 29
FC2_MODE_30
FC2_MODE_31
FC2_NUM_MODES Number of modes.
FC2_MODE_FORCE_32BITS
```

5.23 Enumerations 111

5.23.2.14 enum fc2PCleBusSpeed

Enumerator

FC2_PCIE_BUSSPEED_2_5
FC2_PCIE_BUSSPEED_UNKNOWN 5.0 Gb/s

FC2_PCIE_BUSSPEED_FORCE_32BITS Speed is unknown.

5.23.2.15 enum fc2PixelFormat

Pixel formats available for Format7 modes.

Enumerator

FC2_PIXEL_FORMAT_MONO8 8 bits of mono information.

FC2_PIXEL_FORMAT_411YUV8 YUV 4:1:1.

FC2_PIXEL_FORMAT_422YUV8 YUV 4:2:2.

FC2 PIXEL FORMAT 444YUV8 YUV 4:4:4.

 $FC2_PIXEL_FORMAT_RGB8$ R = G = B = 8 bits.

FC2_PIXEL_FORMAT_MONO16 16 bits of mono information.

 $FC2_PIXEL_FORMAT_RGB16$ R = G = B = 16 bits.

FC2_PIXEL_FORMAT_S_MONO16 16 bits of signed mono information.

 $FC2_PIXEL_FORMAT_S_RGB16$ R = G = B = 16 bits signed.

FC2_PIXEL_FORMAT_RAW8 8 bit raw data output of sensor.

FC2_PIXEL_FORMAT_RAW16 16 bit raw data output of sensor.

FC2_PIXEL_FORMAT_MONO12 12 bits of mono information.

FC2_PIXEL_FORMAT_RAW12 12 bit raw data output of sensor.

FC2_PIXEL_FORMAT_BGR 24 bit BGR.

FC2_PIXEL_FORMAT_BGRU 32 bit BGRU.

FC2 PIXEL FORMAT RGB 24 bit RGB.

FC2_PIXEL_FORMAT_RGBU 32 bit RGBU.

FC2_PIXEL_FORMAT_BGR16 R = G = B = 16 bits.

FC2_PIXEL_FORMAT_BGRU16 64 bit BGRU.

FC2_PIXEL_FORMAT_422YUV8_JPEG JPEG compressed stream.

FC2_NUM_PIXEL_FORMATS Number of pixel formats.

FC2_UNSPECIFIED_PIXEL_FORMAT Unspecified pixel format.

5.23.2.16 enum fc2PropertyType

Camera properties.

Not all properties may be supported, depending on the camera model.

Enumerator

FC2_BRIGHTNESS

FC2 AUTO EXPOSURE

FC2_SHARPNESS

FC2_WHITE_BALANCE

FC2_HUE

FC2_SATURATION

FC2 GAMMA

FC2_IRIS

FC2_FOCUS

FC2_ZOOM

FC2_PAN

FC2_TILT

FC2 SHUTTER

FC2_GAIN

FC2_TRIGGER_MODE

FC2_TRIGGER_DELAY

FC2_FRAME_RATE

FC2_TEMPERATURE

FC2_UNSPECIFIED_PROPERTY_TYPE

FC2_PROPERTY_TYPE_FORCE_32BITS

5.23.2.17 enum fc2VideoMode

DCAM video modes.

Enumerator

FC2_VIDEOMODE_160x120YUV444 160x120 YUV444.

FC2_VIDEOMODE_320x240YUV422 320x240 YUV422.

FC2_VIDEOMODE_640x480YUV411 640x480 YUV411.

FC2 VIDEOMODE 640x480YUV422 640x480 YUV422.

FC2_VIDEOMODE_640x480RGB 640x480 24-bit RGB.

FC2_VIDEOMODE_640x480Y8 640x480 8-bit.

FC2_VIDEOMODE_640x480Y16 640x480 16-bit.

FC2_VIDEOMODE_800x600YUV422 800x600 YUV422.

FC2_VIDEOMODE_800x600RGB 800x600 RGB.

FC2_VIDEOMODE_800x600Y8 800x600 8-bit.

FC2_VIDEOMODE_800x600Y16 800x600 16-bit.

FC2_VIDEOMODE_1024x768YUV422 1024x768 YUV422.

5.23 Enumerations 113

- FC2_VIDEOMODE_1024x768RGB 1024x768 RGB.
- FC2_VIDEOMODE_1024x768Y8 1024x768 8-bit.
- FC2_VIDEOMODE_1024x768Y16 1024x768 16-bit.
- FC2_VIDEOMODE_1280x960YUV422 1280x960YUV422.
- FC2_VIDEOMODE_1280x960RGB 1280x960 RGB.
- FC2_VIDEOMODE_1280x960Y8 1280x960 8-bit.
- FC2_VIDEOMODE_1280x960Y16 1280x960 16-bit.
- FC2_VIDEOMODE_1600x1200YUV422 1600x1200 YUV422.
- FC2_VIDEOMODE_1600x1200RGB 1600x1200 RGB.
- FC2_VIDEOMODE_1600x1200Y8 1600x1200 8-bit.
- FC2_VIDEOMODE_1600x1200Y16 1600x1200 16-bit.
- FC2_VIDEOMODE_FORMAT7 Custom video mode for Format7 functionality.
- FC2_NUM_VIDEOMODES Number of possible video modes.
- FC2_VIDEOMODE_FORCE_32BITS

5.24 GigE specific enumerations

These enumerations are specific to GigE camera operation only.

Enumerations

```
    enum fc2GigEPropertyType {
        FC2_HEARTBEAT,
        FC2_HEARTBEAT_TIMEOUT,
        PACKET_SIZE,
        PACKET_DELAY }
```

Possible properties that can be queried from the camera.

5.24.1 Detailed Description

These enumerations are specific to GigE camera operation only.

5.24.2 Enumeration Type Documentation

5.24.2.1 enum fc2GigEPropertyType

Possible properties that can be queried from the camera.

Enumerator

FC2_HEARTBEAT
FC2_HEARTBEAT_TIMEOUT
PACKET_SIZE
PACKET_DELAY

5.25 Structures 115

5.25 Structures

Collaboration diagram for Structures:

Modules

• GigE specific structures

These structures are specific to GigE camera operation only.

· IIDC specific structures

These structures are specific to IIDC camera operation only.

· Image saving structures.

These structures define various parameters used for saving images.

Data Structures

- struct fc2Image
- struct fc2SystemInfo

Description of the system.

struct fc2Version

The current version of the library.

• struct fc2IPAddress

IPv4 address.

struct fc2Format7ImageSettings

Format 7 image settings.

struct fc2Config

Configuration for a camera.

• struct fc2TriggerDelayInfo

Information about a specific camera property.

struct fc2TriggerDelay

A specific camera property.

struct fc2TriggerModeInfo

Information about a camera trigger property.

• struct fc2TriggerMode

A camera trigger.

struct fc2StrobeInfo

A camera strobe property.

struct fc2StrobeControl

A camera strobe.

struct fc2TimeStamp

Timestamp information.

struct fc2ConfigROM

Camera configuration ROM.

struct fc2CameraInfo

Camera information.

struct fc2EmbeddedImageInfoProperty

Properties of a single embedded image info property.

· struct fc2EmbeddedImageInfo

Properties of the possible embedded image information.

• struct fc2ImageMetadata

116 Module Documentation

Metadata related to an image.

• struct fc2LUTData

Information about the camera's look up table.

• struct fc2CameraStats

Camera diagnostic information.

• struct fc2PNGOption

Options for saving PNG images.

5.25.1 Detailed Description

5.26 GigE specific structures

These structures are specific to GigE camera operation only.

Collaboration diagram for GigE specific structures:

Data Structures

struct fc2IPAddress

IPv4 address.

struct fc2MACAddress

MAC address.

struct fc2GigEProperty

A GigE property.

• struct fc2GigEStreamChannel

Information about a single GigE stream channel.

struct fc2GigEConfig

Configuration for a GigE camera.

• struct fc2GigEImageSettingsInfo

Format 7 information for a single mode.

struct fc2GigEImageSettings

Image settings for a GigE camera.

5.26.1 Detailed Description

These structures are specific to GigE camera operation only.

118 Module Documentation

5.27 IIDC specific structures

These structures are specific to IIDC camera operation only.

Collaboration diagram for IIDC specific structures:

Data Structures

• struct fc2Format7ImageSettings

Format 7 image settings.

• struct fc2Format7Info

Format 7 information for a single mode.

struct fc2Format7PacketInfo

Format 7 packet information.

5.27.1 Detailed Description

These structures are specific to IIDC camera operation only.

5.28 Image saving structures.

These structures define various parameters used for saving images.

Collaboration diagram for Image saving structures.:

Data Structures

struct fc2PNGOption

Options for saving PNG images.

• struct fc2PPMOption

Options for saving PPM images.

· struct fc2PGMOption

Options for saving PGM images.

• struct fc2TIFFOption

Options for saving TIFF images.

struct fc2JPEGOption

Options for saving JPEG image.

• struct fc2JPG2Option

Options for saving JPEG2000 image.

• struct fc2BMPOption

Options for saving Bitmap image.

• struct fc2MJPGOption

Options for saving MJPG files.

struct fc2H264Option

Options for saving H264 files.

struct fc2AVIOption

Options for saving AVI files.

struct fc2EventOptions

Options for enabling device event registration.

struct fc2EventCallbackData

Typedefs

- typedef void * fc2CallbackHandle
- typedef void(* fc2BusEventCallback) (void *pParameter, unsigned int serialNumber)
- typedef void(* fc2lmageEventCallback) (fc2lmage *image, void *pCallbackData)
- typedef void(* fc2AsyncCommandCallback) (fc2Error retError, void *pUserData)
- typedef void(* fc2CameraEventCallback) (void *pCallbackData)

Enumerations

```
    enum fc2TIFFCompressionMethod {
        FC2_TIFF_NONE = 1,
        FC2_TIFF_PACKBITS,
        FC2_TIFF_DEFLATE,
        FC2_TIFF_ADOBE_DEFLATE,
        FC2_TIFF_CCITTFAX3,
        FC2_TIFF_CCITTFAX4,
        FC2_TIFF_LZW,
        FC2_TIFF_JPEG }
```

120 Module Documentation

5.28.1 Detailed Description

These structures define various parameters used for saving images.

5.28.2 Typedef Documentation

- 5.28.2.1 typedef void(* fc2AsyncCommandCallback) (fc2Error retError, void *pUserData)
- 5.28.2.2 typedef void(* fc2BusEventCallback) (void *pParameter, unsigned int serialNumber)
- 5.28.2.3 typedef void* fc2CallbackHandle
- 5.28.2.4 typedef void(* fc2CameraEventCallback) (void *pCallbackData)
- 5.28.2.5 typedef void(* fc2lmageEventCallback) (fc2lmage *image, void *pCallbackData)

5.28.3 Enumeration Type Documentation

5.28.3.1 enum fc2TIFFCompressionMethod

Enumerator

- FC2_TIFF_NONE Save without any compression.
- FC2_TIFF_PACKBITS Save using PACKBITS compression.
- FC2_TIFF_DEFLATE Save using DEFLATE compression (ZLIB compression).
- FC2_TIFF_ADOBE_DEFLATE Save using ADOBE DEFLATE compression.
- **FC2_TIFF_CCITTFAX3** Save using CCITT Group 3 fax encoding. This is only valid for 1-bit images only. Default to LZW for other bit depths.
- **FC2_TIFF_CCITTFAX4** Save using CCITT Group 4 fax encoding. This is only valid for 1-bit images only. Default to LZW for other bit depths.
- FC2_TIFF_LZW Save using LZW compression.
- **FC2_TIFF_JPEG** Save using JPEG compression. This is only valid for 8-bit greyscale and 24-bit only. Default to LZW for other bit depths.

Chapter 6

Data Structure Documentation

6.1 fc2AVIOption Struct Reference

Options for saving AVI files.

Data Fields

float frameRate

Frame rate of the stream.

• unsigned int reserved [256]

Reserved for future use.

6.1.1 Detailed Description

Options for saving AVI files.

6.1.2 Field Documentation

6.1.2.1 float frameRate

Frame rate of the stream.

6.1.2.2 unsigned int reserved[256]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.2 fc2BMPOption Struct Reference

Options for sa	avina	Bitmap	image.
----------------	-------	--------	--------

Data Fields

- BOOL indexedColor_8bit
- unsigned int reserved [16]

Reserved for future use.

6.2.1 Detailed Description

Options for saving Bitmap image.

- 6.2.2 Field Documentation
- 6.2.2.1 BOOL indexedColor_8bit
- 6.2.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.3 fc2CameraInfo Struct Reference

Camera information.

Collaboration diagram for fc2CameraInfo:

Data Fields

· unsigned int serialNumber

Device serial number.

fc2InterfaceType interfaceType

Interface type.

• fc2DriverType driverType

Driver type.

· BOOL isColorCamera

Flag indicating if this is a color camera.

char modelName [MAX_STRING_LENGTH]

Device model name.

• char vendorName [MAX_STRING_LENGTH]

Device vendor name.

• char sensorInfo [MAX_STRING_LENGTH]

String detailing the sensor information.

char sensorResolution [MAX_STRING_LENGTH]

String providing the sensor resolution.

• char driverName [MAX_STRING_LENGTH]

Driver name of driver being used.

char firmwareVersion [MAX_STRING_LENGTH]

Firmware version of camera.

• char firmwareBuildTime [MAX_STRING_LENGTH]

Firmware build time.

fc2BusSpeed maximumBusSpeed

Maximum bus speed.

fc2BayerTileFormat bayerTileFormat

Bayer tile format.

• fc2PCleBusSpeed pcieBusSpeed

Bus number, set to 0 for GigE and USB cameras.

unsigned short nodeNumber

ieee1394 Node number, set to 0 for GigE and USB cameras

• unsigned short busNumber

PCIe Bus Speed, set to PCIE_BUSSPEED_UNKNOWN for unsupported drivers.

• unsigned int reserved [16]

Reserved for future use.

IIDC specific information

· unsigned int iidcVer

DCAM version.

• fc2ConfigROM configROM

Configuration ROM data.

GigE specific information

• unsigned int gigEMajorVersion

GigE Vision version.

• unsigned int gigEMinorVersion

GigE Vision minor version.

char userDefinedName [MAX_STRING_LENGTH]

User defined name.

• char xmlURL1 [MAX_STRING_LENGTH]

XML URL 1.

• char xmlURL2 [MAX_STRING_LENGTH]

XML URL 2.

fc2MACAddress macAddress

MAC address.

• fc2IPAddress ipAddress

IP address.

· fc2IPAddress subnetMask

Subnet mask.

• fc2IPAddress defaultGateway

Default gateway.

• unsigned int ccpStatus

Status/Content of CCP register.

• unsigned int applicationIPAddress

Local Application IP Address.

• unsigned int applicationPort

Local Application port.

6.3.1 Detailed Description

Camera information.

6.3.2 Field Documentation

6.3.2.1 unsigned int applicationIPAddress

Local Application IP Address.

6.3.2.2 unsigned int applicationPort

Local Application port.

6.3.2.3 fc2BayerTileFormat bayerTileFormat

Bayer tile format.

6.3.2.4 unsigned short busNumber

PCIe Bus Speed, set to PCIE_BUSSPEED_UNKNOWN for unsupported drivers.

6.3.2.5 unsigned int ccpStatus

Status/Content of CCP register.

Generated by Doxygen

6.3.2.6 fc2ConfigROM configROM
Configuration ROM data.
6.3.2.7 fc2IPAddress defaultGateway
Default gateway.
6.3.2.8 char driverName[MAX_STRING_LENGTH]
Driver name of driver being used.
6.3.2.9 fc2DriverType driverType
Driver type.
6.3.2.10 char firmwareBuildTime[MAX_STRING_LENGTH]
Firmware build time.
6.3.2.11 char firmwareVersion[MAX_STRING_LENGTH]
Firmware version of camera.
6.3.2.12 unsigned int gigEMajorVersion
GigE Vision version.
6.3.2.13 unsigned int gigEMinorVersion
GigE Vision minor version.
6.3.2.14 unsigned int iidcVer
DCAM version.
6.3.2.15 fc2InterfaceType interfaceType
Interface type.

String providing the sensor resolution.

6.3.2.16 fc2IPAddress ipAddress
IP address.
6.3.2.17 BOOL isColorCamera
Flag indicating if this is a color camera.
6.3.2.18 fc2MACAddress macAddress
MAC address.
6.3.2.19 fc2BusSpeed maximumBusSpeed
Maximum bus speed.
6.3.2.20 char modelName[MAX_STRING_LENGTH]
Device model name.
6.3.2.21 unsigned short nodeNumber
ieee1394 Node number, set to 0 for GigE and USB cameras
6.3.2.22 fc2PCleBusSpeed pcieBusSpeed
Bus number, set to 0 for GigE and USB cameras.
6.3.2.23 unsigned int reserved[16]
Reserved for future use.
6.3.2.24 char sensorInfo[MAX_STRING_LENGTH]
String detailing the sensor information.
6.3.2.25 char sensorResolution[MAX_STRING_LENGTH]
String providing the conser recolution

6.3.2.26 unsigned int serialNumber	
Device serial number.	
6.3.2.27 fc2IPAddress subnetMask	
Subnet mask.	
6.3.2.28 char userDefinedName[MAX_STRING_LENGTH]	
User defined name.	
6.3.2.29 char vendorName[MAX_STRING_LENGTH]	
Device vendor name.	
6.3.2.30 char xmlURL1[MAX_STRING_LENGTH]	
XML URL 1.	
6.3.2.31 char xmlURL2[MAX_STRING_LENGTH]	
XML URL 2.	
The documentation for this struct was generated from the following file:	
• FlyCapture2Defs_C.h	
6.4 fc2CameraStats Struct Reference	
Camera diagnostic information.	
Collaboration diagram for fc2CameraStats:	

Data Fields

- · unsigned int imageDropped
- · unsigned int imageCorrupt
- · unsigned int imageXmitFailed
- unsigned int imageDriverDropped
- · unsigned int regReadFailed
- · unsigned int regWriteFailed
- unsigned int portErrors
- BOOL cameraPowerUp
- float cameraVoltages [8]
- unsigned int numVoltages

The number of voltage registers available.

- float cameraCurrents [8]
- unsigned int numCurrents

The number of current registers available.

- unsigned int temperature
- unsigned int timeSinceInitialization
- unsigned int timeSinceBusReset
- fc2TimeStamp timeStamp
- unsigned int numResendPacketsRequested
- · unsigned int numResendPacketsReceived
- unsigned int reserved [16]

Reserved for future use.

6.4.1 Detailed Description

Camera diagnostic information.

- 6.4.2 Field Documentation
- 6.4.2.1 float cameraCurrents[8]
- 6.4.2.2 BOOL cameraPowerUp
- 6.4.2.3 float cameraVoltages[8]
- 6.4.2.4 unsigned int imageCorrupt
- 6.4.2.5 unsigned int imageDriverDropped
- 6.4.2.6 unsigned int imageDropped
- 6.4.2.7 unsigned int imageXmitFailed
- 6.4.2.8 unsigned int numCurrents

The number of current registers available.

0: the values in cameraCurrents[] are invalid.

6.4.2.9 unsigned int numResendPacketsReceived	
6.4.2.10 unsigned int numResendPacketsRequested	
6.4.2.11 unsigned int numVoltages	
The number of voltage registers available.	
0: the values in cameraVoltages[] are invalid.	
6.4.2.12 unsigned int portErrors	
6.4.2.13 unsigned int regReadFailed	
6.4.2.14 unsigned int regWriteFailed	
6.4.2.15 unsigned int reserved[16]	
Reserved for future use.	
6.4.2.16 unsigned int temperature	
6.4.2.17 unsigned int timeSinceBusReset	
6.4.2.18 unsigned int timeSinceInitialization	
6.4.2.19 fc2TimeStamp timeStamp	
The documentation for this struct was generated from the following file:	
• FlyCapture2Defs_C.h	

6.5 fc2Config Struct Reference

Configuration for a camera.

Data Fields

· unsigned int numBuffers

Number of buffers used by the FlyCapture2 library to grab images.

· unsigned int numImageNotifications

Number of notifications per image.

• unsigned int minNumImageNotifications

Minimum number of notifications needed for the current image settings on the camera.

int grabTimeout

Time in milliseconds that RetrieveBuffer() and WaitForBufferEvent() will wait for an image before timing out and returning.

• fc2GrabMode grabMode

Grab mode for the camera.

BOOL highPerformanceRetrieveBuffer

This parameter enables RetrieveBuffer to run in high performance mode.

· fc2BusSpeed isochBusSpeed

Isochronous bus speed.

· fc2BusSpeed asyncBusSpeed

Asynchronous bus speed.

fc2BandwidthAllocation bandwidthAllocation

Bandwidth allocation flag that tells the camera the bandwidth allocation strategy to employ.

· unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library.

unsigned int registerTimeout

Register read/write timeout value, in microseconds.

• unsigned int reserved [16]

Reserved for future use.

6.5.1 Detailed Description

Configuration for a camera.

These options are options that are generally should be set before starting isochronous transfer.

6.5.2 Field Documentation

6.5.2.1 fc2BusSpeed asyncBusSpeed

Asynchronous bus speed.

6.5.2.2 fc2BandwidthAllocation bandwidthAllocation

Bandwidth allocation flag that tells the camera the bandwidth allocation strategy to employ.

6.5.2.3 fc2GrabMode grabMode

Grab mode for the camera.

The default is DROP_FRAMES.

6.5.2.4 int grabTimeout

Time in milliseconds that RetrieveBuffer() and WaitForBufferEvent() will wait for an image before timing out and returning.

6.5.2.5 BOOL highPerformanceRetrieveBuffer

This parameter enables RetrieveBuffer to run in high performance mode.

This means that any interaction with the camera, other than grabbing the image is disabled. Currently Retrieve buffer reads registers on the camera to determine which embedded image information settings have been enabled, and it reads what the bayer tile is currently set to. When High Performance mode is on, these reads are disabled. This means that any changes to the Bayer Tile or to the Embedded image info after StartCapture() will not be tracked when made using direct register writes. If the corresponding SetEmbededImageInfo() and GetEmbededImageInfo() calls are used then the changes will be appropriately reflected. This also means that changes to embedded image info from other processes will not be updated either.

6.5.2.6 fc2BusSpeed isochBusSpeed

Isochronous bus speed.

6.5.2.7 unsigned int minNumImageNotifications

Minimum number of notifications needed for the current image settings on the camera.

Read-only value.

6.5.2.8 unsigned int numBuffers

Number of buffers used by the FlyCapture2 library to grab images.

6.5.2.9 unsigned int numImageNotifications

Number of notifications per image.

This value should only be set after the image settings to be used is set to the camera. The default number of notifications is 1.

There are 4 general scenarios:

- · 1 notification End of image
- · 2 notifications After first packet and end of image
- · 3 notifications After first packet, middle of image, end of image
- x notifications After first packet, (x -2) spread evenly, end of image

Specifying zero for the number of notifications will be ignored (the current value will not be modified).

Note that the event numbers start at 0. Ex. when 3 notifications are used, the three events will be 0, 1 and 2.

6.5.2.10 unsigned int registerTimeout

Register read/write timeout value, in microseconds.

The default value is dependent on the interface type.

6.5.2.11 unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library.

The default value is 0.

6.5.2.12 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.6 fc2ConfigROM Struct Reference

Camera configuration ROM.

Data Fields

· unsigned int nodeVendorld

Vendor ID of a node.

• unsigned int chipIdHi

Chip ID (high part).

· unsigned int chipIdLo

Chip ID (low part).

• unsigned int unitSpecId

Unit Spec ID, usually 0xa02d.

• unsigned int unitSWVer

Unit software version.

unsigned int unitSubSWVer

Unit sub software version.

• unsigned int vendorUniqueInfo_0

Vendor unique info 0.

• unsigned int vendorUniqueInfo_1

Vendor unique info 1.

• unsigned int vendorUniqueInfo_2

Vendor unique info 2.

• unsigned int vendorUniqueInfo_3

Vendor unique info 3.

char pszKeyword [MAX_STRING_LENGTH]

Keyword.

• unsigned int reserved [16]

Reserved for future use.

Generated by Doxygen

6.6.1	Detailed Description
Camer	a configuration ROM.
6.6.2	Field Documentation
6.6.2.1	unsigned int chipIdHi
Chip II	O (high part).
6.6.2.2	unsigned int chipldLo
Chip II	O (low part).
6.6.2.3	unsigned int nodeVendorld
Vendo	ID of a node.
6.6.2.4	char pszKeyword[MAX_STRING_LENGTH]
Keywo	rd.
6.6.2.5	unsigned int reserved[16]
Reserv	ved for future use.
6.6.2.6	unsigned int unitSpecId
Unit Sp	pec ID, usually 0xa02d.
6.6.2.7	unsigned int unitSubSWVer
Unit su	b software version.
6.6.2.8	unsigned int unitSWVer
Unit so	oftware version.
6.6.2.9	unsigned int vendorUniqueInfo_0
Vendo	r unique info 0.

6.6.2.10 unsigned int vendorUniqueInfo_1
Vendor unique info 1.
6.6.2.11 unsigned int vendorUniqueInfo_2
Vendor unique info 2.
6.6.2.12 unsigned int vendorUniqueInfo_3

Vendor unique info 3.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.7 fc2EmbeddedImageInfo Struct Reference

Properties of the possible embedded image information.

Collaboration diagram for fc2EmbeddedImageInfo:

Data Fields

- fc2EmbeddedImageInfoProperty timestamp
- fc2EmbeddedImageInfoProperty gain
- · fc2EmbeddedImageInfoProperty shutter
- fc2EmbeddedImageInfoProperty brightness
- fc2EmbeddedImageInfoProperty exposure
- $\bullet \ \ fc 2 Embedded Image Info Property\ white Balance$
- fc2EmbeddedImageInfoProperty frameCounter
- fc2EmbeddedImageInfoProperty strobePattern
- fc2EmbeddedImageInfoProperty GPIOPinState
- fc2EmbeddedImageInfoProperty ROIPosition

6.7.1 Detailed Description

Properties of the possible embedded image information.

6.7.2	Field Documentation
6.7.2.1	fc2EmbeddedImageInfoProperty brightness
6.7.2.2	fc2EmbeddedImageInfoProperty exposure
6.7.2.3	fc2EmbeddedImageInfoProperty frameCounter
6.7.2.4	fc2EmbeddedImageInfoProperty gain
6.7.2.5	fc2EmbeddedImageInfoProperty GPIOPinState
6.7.2.6	fc2EmbeddedImageInfoProperty ROIPosition
6.7.2.7	fc2EmbeddedImageInfoProperty shutter

6.7.2.8 fc2EmbeddedImageInfoProperty strobePattern

 ${\bf 6.7.2.9} \quad \textbf{fc2EmbeddedImageInfoProperty timestamp} \\$

6.7.2.10 fc2EmbeddedImageInfoProperty whiteBalance

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.8 fc2EmbeddedImageInfoProperty Struct Reference

Properties of a single embedded image info property.

Data Fields

BOOL available

Whether this property is available.

• BOOL onOff

Whether this property is on or off.

6.8.1 Detailed Description

Properties of a single embedded image info property.

6.8.2 Field Documentation

6.8.2.1 BOOL available

Whether this property is available.

6.8.2.2 BOOL onOff

Whether this property is on or off.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.9 fc2EventCallbackData Struct Reference

Data Fields

void * EventUserData

Pointer to the user-supplied data struct.

size_t EventUserDataSize

Size of the user data supplied to the RegisterEvent() function.

• const char * EventName

The event name used to register the event.

unsigned long long EventID

The device register which EventName maps to.

unsigned long long EventTimestamp

Timestamp indicated the time (as reported by the camera) at which the camera exposure operation completed.

void * EventData

A pointer to additional data pertaining to the event which just trigger the callback function.

• size_t EventDataSize

The size of the structure pointed to by EventData.

6.9.1 Field Documentation

6.9.1.1 void* EventData

A pointer to additional data pertaining to the event which just trigger the callback function.

The data may be of difference sizes or may not even be allocated, depending on the type of event which triggered the callback.

6.9.1.2 size_t EventDataSize

The size of the structure pointed to by EventData.

This value should be checked, especially if there are events which can trigger variable-length event data to be returned to the user when the callback function is issued.

6.9.1.3 unsigned long long EventID

The device register which EventName maps to.

Provides an alternate means of indexing into different event types.

6.9.1.4 const char* EventName

The event name used to register the event.

Provided so the user knows which event triggered the callback.

6.9.1.5 unsigned long long EventTimestamp

Timestamp indicated the time (as reported by the camera) at which the camera exposure operation completed.

This can be compared with image timestamps if there is a need to map event timestamps to specific images, if applicable.

6.9.1.6 void* EventUserData

Pointer to the user-supplied data struct.

6.9.1.7 size_t EventUserDataSize

Size of the user data supplied to the RegisterEvent() function.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.10 fc2EventOptions Struct Reference

Options for enabling device event registration.

Data Fields

fc2CameraEventCallback EventCallbackFcn

Callback function pointer.

• const char * EventName

Event name to register.

const void * EventUserData

Pointer to callback data to be passed to the callback function.

• size_t EventUserDataSize

Size of the underlying struct passed as eventCallbackData for sanity checks.

6.10.1 Detailed Description

Options for enabling device event registration.

6.10.2 Field Documentation

6.10.2.1 fc2CameraEventCallback EventCallbackFcn

Callback function pointer.

6.10.2.2 const char* EventName

Event name to register.

6.10.2.3 const void* EventUserData

Pointer to callback data to be passed to the callback function.

6.10.2.4 size_t EventUserDataSize

Size of the underlying struct passed as eventCallbackData for sanity checks.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.11 fc2Format7ImageSettings Struct Reference

Format 7 image settings.

Data Fields

· fc2Mode mode

Format 7 mode.

· unsigned int offsetX

Horizontal image offset.

· unsigned int offsetY

Vertical image offset.

· unsigned int width

Width of image.

· unsigned int height

Height of image.

fc2PixelFormat pixelFormat

Pixel format of image.

• unsigned int reserved [8]

Reserved for future use.

6.11.1 Detailed Description Format 7 image settings. 6.11.2 Field Documentation 6.11.2.1 unsigned int height Height of image. 6.11.2.2 fc2Mode mode Format 7 mode. 6.11.2.3 unsigned int offsetX Horizontal image offset. 6.11.2.4 unsigned int offsetY Vertical image offset. 6.11.2.5 fc2PixelFormat pixelFormat Pixel format of image. 6.11.2.6 unsigned int reserved[8] Reserved for future use. 6.11.2.7 unsigned int width Width of image.

FlyCapture2Defs_C.h

6.12 fc2Format7Info Struct Reference

The documentation for this struct was generated from the following file:

Format 7 information for a single mode.

Data Fields

• fc2Mode mode

Format 7 mode.

• unsigned int maxWidth

Maximum image width.

· unsigned int maxHeight

Maximum image height.

• unsigned int offsetHStepSize

Horizontal step size for the offset.

• unsigned int offsetVStepSize

Vertical step size for the offset.

• unsigned int imageHStepSize

Horizontal step size for the image.

• unsigned int imageVStepSize

Vertical step size for the image.

• unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

• unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

• unsigned int packetSize

Current packet size in bytes.

• unsigned int minPacketSize

Minimum packet size in bytes for current mode.

unsigned int maxPacketSize

Maximum packet size in bytes for current mode.

float percentage

Current packet size as a percentage of maximum packet size.

• unsigned int reserved [16]

Reserved for future use.

6.12.1 Detailed Description

Format 7 information for a single mode.

6.12.2 Field Documentation

6.12.2.1 unsigned int imageHStepSize

Horizontal step size for the image.

6.12.2.2 unsigned int imageVStepSize

Vertical step size for the image.

Generated by Doxygen

6.12.2.3 unsigned int maxHeight
Maximum image height.
6.12.2.4 unsigned int maxPacketSize
Maximum packet size in bytes for current mode.
6.12.2.5 unsigned int maxWidth
Maximum image width.
6.12.2.6 unsigned int minPacketSize
Minimum packet size in bytes for current mode.
6.12.2.7 fc2Mode mode
Format 7 mode.
6.12.2.8 unsigned int offsetHStepSize
Horizontal step size for the offset.
6.12.2.9 unsigned int offsetVStepSize
Vertical step size for the offset.
6.12.2.10 unsigned int packetSize
Current packet size in bytes.
6.12.2.11 float percentage
Current packet size as a percentage of maximum packet size.
6.12.2.12 unsigned int pixelFormatBitField
Supported pixel formats in a bit field.

6.12.2.13 unsigned int reserved[16]

Reserved for future use.

6.12.2.14 unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs C.h

6.13 fc2Format7PacketInfo Struct Reference

Format 7 packet information.

Data Fields

- unsigned int recommendedBytesPerPacket
 - Recommended bytes per packet.
- unsigned int maxBytesPerPacket
 - Maximum bytes per packet.
- · unsigned int unitBytesPerPacket
 - Minimum bytes per packet.
- unsigned int reserved [8]

Reserved for future use.

6.13.1 Detailed Description

Format 7 packet information.

6.13.2 Field Documentation

6.13.2.1 unsigned int maxBytesPerPacket

Maximum bytes per packet.

6.13.2.2 unsigned int recommendedBytesPerPacket

Recommended bytes per packet.

6.13.2.3 unsigned int reserved[8]

Reserved for future use.

6.13.2.4 unsigned int unitBytesPerPacket

Minimum bytes per packet.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.14 fc2GigEConfig Struct Reference

Configuration for a GigE camera.

Data Fields

· BOOL enablePacketResend

Turn on/off packet resend functionality.

unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library.

• unsigned int registerTimeout

Register read/write timeout value, in microseconds.

• unsigned int reserved [8]

6.14.1 Detailed Description

Configuration for a GigE camera.

These options are options that are generally should be set before starting isochronous transfer.

6.14.2 Field Documentation

6.14.2.1 BOOL enablePacketResend

Turn on/off packet resend functionality.

6.14.2.2 unsigned int registerTimeout

Register read/write timeout value, in microseconds.

The default value is dependent on the interface type.

6.14.2.3 unsigned int registerTimeoutRetries

Number of retries to perform when a register read/write timeout is received by the library.

The default value is 0.

6.14.2.4 unsigned int reserved[8]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.15 fc2GigElmageSettings Struct Reference

Image settings for a GigE camera.

Data Fields

- · unsigned int offsetX
 - Horizontal image offset.
- · unsigned int offsetY
 - Vertical image offset.
- · unsigned int width
 - Width of image.
- · unsigned int height
 - Height of image.
- fc2PixelFormat pixelFormat
 - Pixel format of image.
- unsigned int reserved [8]

Reserved for future use.

6.15.1 Detailed Description

Image settings for a GigE camera.

6.15.2 Field Documentation

6.15.2.1 unsigned int height

Height of image.

6.15.2.2 unsigned int offsetX

Horizontal image offset.

6.15.2.3 unsigned int offsetY

Vertical image offset.

6.15.2.4 fc2PixelFormat pixelFormat

Pixel format of image.

6.15.2.5 unsigned int reserved[8]

Reserved for future use.

6.15.2.6 unsigned int width

Width of image.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs C.h

6.16 fc2GigElmageSettingsInfo Struct Reference

Format 7 information for a single mode.

Data Fields

· unsigned int maxWidth

Maximum image width.

unsigned int maxHeight

Maximum image height.

• unsigned int offsetHStepSize

Horizontal step size for the offset.

• unsigned int offsetVStepSize

Vertical step size for the offset.

• unsigned int imageHStepSize

Horizontal step size for the image.

• unsigned int imageVStepSize

Vertical step size for the image.

unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

• unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

• unsigned int reserved [16]

Reserved for future use.

6.16.1	Detailed Description
Format	7 information for a single mode.
6.16.2	Field Documentation
6.16.2.1	unsigned int imageHStepSize
Horizon	atal step size for the image.
6.16.2.2	unsigned int imageVStepSize
Vertical	step size for the image.
6.16.2.3	unsigned int maxHeight
Maximu	ım image height.
6.16.2.4	unsigned int maxWidth
Maximu	ım image width.
6.16.2.5	unsigned int offsetHStepSize
Horizon	atal step size for the offset.
6.16.2.6	unsigned int offsetVStepSize
Vertical	step size for the offset.

6.16.2.8 unsigned int reserved[16]

6.16.2.7 unsigned int pixelFormatBitField

Supported pixel formats in a bit field.

Reserved for future use.

6.16.2.9 unsigned int vendorPixelFormatBitField

Vendor unique pixel formats in a bit field.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.17 fc2GigEProperty Struct Reference

A GigE property.

Data Fields

• fc2GigEPropertyType propType

The type of property.

· BOOL isReadable

Whether the property is readable.

· BOOL isWritable

Whether the property is writable.

unsigned int min

Minimum value.

unsigned int max

Maximum value.

· unsigned int value

Current value.

• unsigned int reserved [8]

6.17.1 Detailed Description

A GigE property.

6.17.2 Field Documentation

6.17.2.1 BOOL is Readable

Whether the property is readable.

If this is false, then no other value in this structure is valid.

6.17.2.2 BOOL is Writable

Whether the property is writable.

6.17.2.3 unsigned int max

Maximum value.

6.17.2.4 unsigned int min

Minimum value.

6.17.2.5 fc2GigEPropertyType propType

The type of property.

6.17.2.6 unsigned int reserved[8]

6.17.2.7 unsigned int value

Current value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.18 fc2GigEStreamChannel Struct Reference

Information about a single GigE stream channel.

Collaboration diagram for fc2GigEStreamChannel:

Data Fields

• unsigned int networkInterfaceIndex

Network interface index used (or to use).

unsigned int hostPort

Host port on the PC where the camera will send the data stream.

• BOOL doNotFragment

Disable IP fragmentation of packets.

• unsigned int packetSize

Packet size, in bytes.

unsigned int interPacketDelay

Inter packet delay, in timestamp counter units.

fc2IPAddress destinationIpAddress

Destination IP address.

· unsigned int sourcePort

Source UDP port of the stream channel.

• unsigned int reserved [8]

6.18.1 Detailed Description

Information about a single GigE stream channel.

6.18.2 Field Documentation

6.18.2.1 fc2IPAddress destinationlpAddress

Destination IP address.

It can be a multicast or unicast address.

6.18.2.2 BOOL doNotFragment

Disable IP fragmentation of packets.

6.18.2.3 unsigned int hostPort

Host port on the PC where the camera will send the data stream.

6.18.2.4 unsigned int interPacketDelay

Inter packet delay, in timestamp counter units.

6.18.2.5 unsigned int networkInterfaceIndex

Network interface index used (or to use).

6.18.2.6 unsigned int packetSize

Packet size, in bytes.

6.18.2.7 unsigned int reserved[8]

6.18.2.8 unsigned int sourcePort

Source UDP port of the stream channel.

Read only.

The documentation for this struct was generated from the following file:

FlyCapture2Defs_C.h

6.19 fc2H264Option Struct Reference

Options for saving H264 files.

Data Fields

· float frameRate

Frame rate of the stream.

· unsigned int width

Width of source image.

· unsigned int height

Height of source image.

· unsigned int bitrate

Bitrate to encode at.

• unsigned int reserved [256]

Reserved for future use.

6.19.1 Detailed Description

Options for saving H264 files.

6.19.2 Field Documentation

6.19.2.1 unsigned int bitrate

Bitrate to encode at.

6.19.2.2 float frameRate

Frame rate of the stream.

6.19.2.3 unsigned int height

Height of source image.

6.19.2.4 unsigned int reserved[256]

Reserved for future use.

6.19.2.5 unsigned int width

Width of source image.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.20 fc2Image Struct Reference

Data Fields

- · unsigned int rows
- unsigned int cols
- unsigned int stride
- unsigned char * pData
- unsigned int dataSize
- unsigned int receivedDataSize
- fc2PixelFormat format
- fc2BayerTileFormat bayerFormat
- fc2ImageImpl imageImpl

6.20.1 Field Documentation

- 6.20.1.1 fc2BayerTileFormat bayerFormat
- 6.20.1.2 unsigned int cols
- 6.20.1.3 unsigned int dataSize
- 6.20.1.4 fc2PixelFormat format
- 6.20.1.5 fc2lmagelmpl imagelmpl
- 6.20.1.6 unsigned char* pData
- 6.20.1.7 unsigned int receivedDataSize
- 6.20.1.8 unsigned int rows
- 6.20.1.9 unsigned int stride

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.21 fc2ImageMetadata Struct Reference

Metadata related to an image.

Data Fields

unsigned int embeddedTimeStamp

Embedded timestamp.

unsigned int embeddedGain

Embedded gain.

• unsigned int embeddedShutter

Embedded shutter.

• unsigned int embeddedBrightness

Embedded brightness.

• unsigned int embeddedExposure

Embedded exposure.

• unsigned int embeddedWhiteBalance

Embedded white balance.

unsigned int embeddedFrameCounter

Embedded frame counter.

unsigned int embeddedStrobePattern

Embedded strobe pattern.

• unsigned int embeddedGPIOPinState

Embedded GPIO pin state.

• unsigned int embeddedROIPosition

Embedded ROI position.

• unsigned int reserved [31]

Reserved for future use.

6.21.1 Detailed Description

Metadata related to an image.

6.21.2 Field Documentation

6.21.2.1 unsigned int embeddedBrightness

Embedded brightness.

6.21.2.2 unsigned int embeddedExposure

Embedded exposure.

6.21.2.3 unsigned int embeddedFrameCounter

Embedded frame counter.

6.21.2.4 unsigned int embeddedGain

Embedded gain.

6.21.2.5 unsigned int embeddedGPIOPinState
Embedded GPIO pin state.
6.21.2.6 unsigned int embeddedROIPosition
Embedded ROI position.
6.21.2.7 unsigned int embeddedShutter
Embedded shutter.
6.21.2.8 unsigned int embeddedStrobePattern
Embedded strobe pattern.
6.21.2.9 unsigned int embeddedTimeStamp
Embedded timestamp.
6.21.2.10 unsigned int embeddedWhiteBalance
Embedded white balance.
6.21.2.11 unsigned int reserved[31]
Reserved for future use.
The documentation for this struct was generated from the following file:
FlyCapture2Defs_C.h

6.22 fc2InternalContext Struct Reference

Data Fields

- FlyCapture2::BusManager * pBusMgr
- $\bullet \ \, \mathsf{FlyCapture2} \\ :: Camera \\ \mathsf{Base} * \mathsf{pCamera} \\$

6.22.1 Field Documentation

- 6.22.1.1 FlyCapture2::BusManager* pBusMgr
- 6.22.1.2 FlyCapture2::CameraBase* pCamera

The documentation for this struct was generated from the following file:

· FlyCapture2Internal C.h

6.23 fc2InternalGuiContext Struct Reference

Data Fields

- FlyCapture2::CameraSelectionDlg * pCameraSelectionDlg
- FlyCapture2::CameraControlDlg * pCameraControlDlg

6.23.1 Field Documentation

- 6.23.1.1 FlyCapture2::CameraControlDlg* pCameraControlDlg
- 6.23.1.2 FlyCapture2::CameraSelectionDlg* pCameraSelectionDlg

The documentation for this struct was generated from the following file:

• FlyCapture2Internal_C.h

6.24 fc2InternalImageCallback Struct Reference

Collaboration diagram for fc2InternalImageCallback:

Data Fields

- fc2ImageEventCallback pCallback
- void * pCallbackData

6.24.1 Field Documentation

- 6.24.1.1 fc2ImageEventCallback pCallback
- 6.24.1.2 void* pCallbackData

The documentation for this struct was generated from the following file:

• FlyCapture2Internal_C.h

6.25 fc2IPAddress Struct Reference

IPv4 address.

Data Fields

• unsigned char octets [4]

6.25.1 Detailed Description

IPv4 address.

6.25.2 Field Documentation

6.25.2.1 unsigned char octets[4]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.26 fc2JPEGOption Struct Reference

Options for saving JPEG image.

Data Fields

• BOOL progressive

Whether to save as a progressive JPEG file.

unsigned int quality

JPEG image quality in range (0-100).

• unsigned int reserved [16]

Reserved for future use.

6.26.1 Detailed Description

Options for saving JPEG image.

6.26.2 Field Documentation

6.26.2.1 BOOL progressive

Whether to save as a progressive JPEG file.

6.26.2.2 unsigned int quality

JPEG image quality in range (0-100).

- 100 Superb quality.
- 75 Good quality.
- 50 Normal quality.
- 10 Poor quality.

6.26.2.3 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.27 fc2JPG2Option Struct Reference

Options for saving JPEG2000 image.

Data Fields

- · unsigned int quality
 - JPEG saving quality in range (1-512).
- unsigned int reserved [16]

Reserved for future use.

6.27.1 Detailed Description

Options for saving JPEG2000 image.

6.27.2 Field Documentation

6.27.2.1 unsigned int quality

JPEG saving quality in range (1-512).

6.27.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.28 fc2LUTData Struct Reference

Information about the camera's look up table.

Data Fields

· BOOL supported

Flag indicating if LUT is supported.

· BOOL enabled

Flag indicating if LUT is enabled.

• unsigned int numBanks

The number of LUT banks available (Always 1 for PGR LUT).

· unsigned int numChannels

The number of LUT channels per bank available.

· unsigned int inputBitDepth

The input bit depth of the LUT.

· unsigned int outputBitDepth

The output bit depth of the LUT.

• unsigned int numEntries

The number of entries in the LUT.

• unsigned int reserved [8]

Reserved for future use.

6.28.1 Detailed Description

Information about the camera's look up table.

6.28.2 Field Documentation

6.28.2.1 BOOL enabled

Flag indicating if LUT is enabled.

6.28.2.2 unsigned int inputBitDepth

The input bit depth of the LUT.

MAC address.

6.28.2.3 unsigned int numBanks				
The number of LUT banks available (Always 1 for PGR LUT).				
6.28.2.4 unsigned int numChannels				
The number of LUT channels per bank available.				
6.28.2.5 unsigned int numEntries				
The number of entries in the LUT.				
6.28.2.6 unsigned int outputBitDepth				
The output bit depth of the LUT.				
6.28.2.7 unsigned int reserved[8]				
Reserved for future use.				
6.28.2.8 BOOL supported				
Flag indicating if LUT is supported.				
The documentation for this struct was generated from the following file:				
FlyCapture2Defs_C.h				
6.29 fc2MACAddress Struct Reference				
MAC address.				
Data Fields				
• unsigned char octets [6]				
6.29.1 Detailed Description				

6.29.2 Field Documentation

6.29.2.1 unsigned char octets[6]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.30 fc2MJPGOption Struct Reference

Options for saving MJPG files.

Data Fields

· float frameRate

Frame rate of the stream.

· unsigned int quality

Image quality (1-100)

• unsigned int reserved [256]

6.30.1 Detailed Description

Options for saving MJPG files.

6.30.2 Field Documentation

6.30.2.1 float frameRate

Frame rate of the stream.

6.30.2.2 unsigned int quality

Image quality (1-100)

6.30.2.3 unsigned int reserved[256]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.31 fc2PGMOption Struct Reference

Options for saving PGM images.

Data Fields

• BOOL binaryFile

Whether to save the PPM as a binary file.

• unsigned int reserved [16]

Reserved for future use.

6.31.1 Detailed Description

Options for saving PGM images.

6.31.2 Field Documentation

6.31.2.1 BOOL binaryFile

Whether to save the PPM as a binary file.

6.31.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.32 fc2PGRGuid Struct Reference

A GUID to the camera.

Data Fields

• unsigned int value [4]

6.32.1 Detailed Description

A GUID to the camera.

It is used to uniquely identify a camera.

6.32.2 Field Documentation

6.32.2.1 unsigned int value[4]

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.33 fc2PNGOption Struct Reference

Options for saving PNG images.

Data Fields

· BOOL interlaced

Whether to save the PNG as interlaced.

· unsigned int compressionLevel

Compression level (0-9).

• unsigned int reserved [16]

Reserved for future use.

6.33.1 Detailed Description

Options for saving PNG images.

6.33.2 Field Documentation

6.33.2.1 unsigned int compressionLevel

Compression level (0-9).

0 is no compression, 9 is best compression.

6.33.2.2 BOOL interlaced

Whether to save the PNG as interlaced.

6.33.2.3 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.34 fc2PPMOption Struct Reference

Options for saving PPM images.

Data Fields

· BOOL binaryFile

Whether to save the PPM as a binary file.

• unsigned int reserved [16]

Reserved for future use.

6.34.1 Detailed Description

Options for saving PPM images.

6.34.2 Field Documentation

6.34.2.1 BOOL binaryFile

Whether to save the PPM as a binary file.

6.34.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.35 fc2StrobeControl Struct Reference

A camera strobe.

Data Fields

• unsigned int source

Source value.

· BOOL onOff

Flag controlling on/off.

· unsigned int polarity

Signal polarity.

• float delay

Signal delay (in ms).

float duration

Signal duration (in ms).

• unsigned int reserved [8]

Reserved for future use.

6.35.1 Detailed Description A camera strobe. 6.35.2 Field Documentation 6.35.2.1 float delay Signal delay (in ms). 6.35.2.2 float duration Signal duration (in ms). 6.35.2.3 BOOL onOff Flag controlling on/off. 6.35.2.4 unsigned int polarity Signal polarity. 6.35.2.5 unsigned int reserved[8] Reserved for future use. 6.35.2.6 unsigned int source Source value. The documentation for this struct was generated from the following file: • FlyCapture2Defs_C.h

6.36 fc2Strobelnfo Struct Reference

A camera strobe property.

Data Fields

• unsigned int source

Source value.

BOOL present

Presence of strobe.

BOOL readOutSupported

Flag indicating if strobe value can be read out.

· BOOL onOffSupported

Flag indicating if on/off is supported.

· BOOL polaritySupported

Flag indicating if polarity is supported.

float minValue

Minimum value.

float maxValue

Maximum value.

• unsigned int reserved [8]

Reserved for future use.

6.36.1 Detailed Description

A camera strobe property.

6.36.2 Field Documentation

6.36.2.1 float maxValue

Maximum value.

6.36.2.2 float minValue

Minimum value.

6.36.2.3 BOOL on Off Supported

Flag indicating if on/off is supported.

6.36.2.4 BOOL polaritySupported

Flag indicating if polarity is supported.

6.36.2.5 BOOL present

Presence of strobe.

6.36.2.6 BOOL readOutSupported

Flag indicating if strobe value can be read out.

6.36.2.7 unsigned int reserved[8]

Reserved for future use.

6.36.2.8 unsigned int source

Source value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.37 fc2SystemInfo Struct Reference

Description of the system.

Data Fields

fc2OSType osType

Operating system type as described by OSType.

• char osDescription [MAX_STRING_LENGTH]

Detailed description of the operating system.

• fc2ByteOrder byteOrder

Byte order of the system.

• size_t sysMemSize

Amount of memory available on the system.

char cpuDescription [MAX_STRING_LENGTH]

Detailed description of the CPU.

size_t numCpuCores

Number of cores on all CPUs on the system.

char driverList [MAX_STRING_LENGTH]

List of drivers used.

• char libraryList [MAX_STRING_LENGTH]

List of libraries used.

char gpuDescription [MAX_STRING_LENGTH]

Detailed description of the GPU.

· size_t screenWidth

Screen resolution width in pixels.

size_t screenHeight

Screen resolution height in pixels.

• unsigned int reserved [16]

Reserved for future use.

6.37.2.9 unsigned int reserved[16]

Reserved for future use.

6.37.1	Detailed Description
Descrip	tion of the system.
6.37.2	Field Documentation
6.37.2.1	fc2ByteOrder byteOrder
Byte ord	der of the system.
6.37.2.2	char cpuDescription[MAX_STRING_LENGTH]
Detailed	I description of the CPU.
6.37.2.3	char driverList[MAX_STRING_LENGTH]
List of d	rivers used.
6.37.2.4	char gpuDescription[MAX_STRING_LENGTH]
Detailed	I description of the GPU.
6.37.2.5	char libraryList[MAX_STRING_LENGTH]
List of li	braries used.
6.37.2.6	size_t numCpuCores
Number	of cores on all CPUs on the system.
6.37.2.7	char osDescription[MAX_STRING_LENGTH]
Detailed	I description of the operating system.
6.37.2.8	fc2OSType osType
Operatir	ng system type as described by OSType.

6.37.2.10 size_t screenHeight

Screen resolution height in pixels.

6.37.2.11 size_t screenWidth

Screen resolution width in pixels.

6.37.2.12 size_t sysMemSize

Amount of memory available on the system.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.38 fc2TIFFOption Struct Reference

Options for saving TIFF images.

Data Fields

- fc2TIFFCompressionMethod compression
 - Compression method to use for encoding TIFF images.
- unsigned int reserved [16]

Reserved for future use.

6.38.1 Detailed Description

Options for saving TIFF images.

6.38.2 Field Documentation

6.38.2.1 fc2TIFFCompressionMethod compression

Compression method to use for encoding TIFF images.

6.38.2.2 unsigned int reserved[16]

Reserved for future use.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.39 fc2TimeStamp Struct Reference

Timestamp information.

Data Fields

- long long seconds
 - Seconds.
- unsigned int microSeconds
 - Microseconds.
- unsigned int cycleSeconds
 - 1394 cycle time seconds.
- unsigned int cycleCount
 - 1394 cycle time count.
- unsigned int cycleOffset
 - 1394 cycle time offset.
- unsigned int reserved [8]
 - Reserved for future use.

6.39.1 Detailed Description

Timestamp information.

6.39.2 Field Documentation

- 6.39.2.1 unsigned int cycleCount
- 1394 cycle time count.
- 6.39.2.2 unsigned int cycleOffset
- 1394 cycle time offset.
- 6.39.2.3 unsigned int cycleSeconds
- 1394 cycle time seconds.
- 6.39.2.4 unsigned int microSeconds

Microseconds.

6.39.2.5 unsigned int reserved[8]

Reserved for future use.

6.39.2.6 long long seconds

Seconds.

The documentation for this struct was generated from the following file:

FlyCapture2Defs_C.h

6.40 fc2TriggerDelay Struct Reference

A specific camera property.

Data Fields

• fc2PropertyType type

Property info type.

• BOOL present

Flag indicating if the property is present.

BOOL absControl

Flag controlling absolute mode (real world units) or non-absolute mode (camera internal units).

· BOOL onePush

Flag controlling one push.

• BOOL onOff

Flag controlling on/off.

BOOL autoManualMode

Flag controlling auto.

· unsigned int valueA

Value A (integer).

· unsigned int valueB

Value B (integer).

• float absValue

Floating point value.

• unsigned int reserved [8]

Reserved for future use.

6.40.1 Detailed Description

A specific camera property.

For example, to set the gain to 12dB, set the following values:

- type GAIN
- absControl true
- onePush false
- onOff-true
- autoManualMode false
- absValue 12.0

6.40.2 Field Documentation
6.40.2.1 BOOL absControl
Flag controlling absolute mode (real world units) or non-absolute mode (camera internal units).
6.40.2.2 float absValue
Floating point value.
Used to configure properties in absolute mode.
6.40.2.3 BOOL autoManualMode
Flag controlling auto.
6.40.2.4 BOOL onePush
Flag controlling one push.
6.40.2.5 BOOL onOff
Flag controlling on/off.
6.40.2.6 BOOL present
Flag indicating if the property is present.
6.40.2.7 unsigned int reserved[8]
Reserved for future use.
6.40.2.8 fc2PropertyType type
Property info type.
6.40.2.9 unsigned int valueA
Value A (integer).
Used to configure properties in non-absolute mode.

6.40.2.10 unsigned int valueB

Value B (integer).

For white balance, value B applies to the blue value and value A applies to the red value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.41 fc2TriggerDelayInfo Struct Reference

Information about a specific camera property.

Data Fields

fc2PropertyType type

Property info type.

BOOL present

Flag indicating if the property is present.

· BOOL autoSupported

Flag indicating if auto is supported.

BOOL manualSupported

Flag indicating if manual is supported.

· BOOL onOffSupported

Flag indicating if on/off is supported.

· BOOL onePushSupported

Flag indicating if one push is supported.

BOOL absValSupported

Flag indicating if absolute mode is supported.

BOOL readOutSupported

Flag indicating if property value can be read out.

unsigned int min

Minimum value (as an integer).

unsigned int max

Maximum value (as an integer).

· float absMin

Minimum value (as a floating point value).

float absMax

Maximum value (as a floating point value).

char pUnits [MAX_STRING_LENGTH]

Textual description of units.

char pUnitAbbr [MAX_STRING_LENGTH]

Abbreviated textual description of units.

• unsigned int reserved [8]

Reserved for future use.

6.41.1 Detailed Description

Information about a specific camera property.

This structure is also also used as the TriggerDelayInfo structure.

6.41.2 Field Documentation

6.41.2.1 float absMax

Maximum value (as a floating point value).

6.41.2.2 float absMin

Minimum value (as a floating point value).

6.41.2.3 BOOL absValSupported

Flag indicating if absolute mode is supported.

6.41.2.4 BOOL autoSupported

Flag indicating if auto is supported.

6.41.2.5 BOOL manual Supported

Flag indicating if manual is supported.

6.41.2.6 unsigned int max

Maximum value (as an integer).

6.41.2.7 unsigned int min

Minimum value (as an integer).

6.41.2.8 BOOL onePushSupported

Flag indicating if one push is supported.

6.41.2.9 BOOL onOffSupported					
Flag indicating if on/off is supported.					
6.41.2.10 BOOL present					
Flag indicating if the property is present.					
6.41.2.11 char pUnitAbbr[MAX_STRING_LENGTH]					
Abbreviated textual description of units.					
6.41.2.12 char pUnits[MAX_STRING_LENGTH]					
Textual description of units.					
6.41.2.13 BOOL readOutSupported					
Flag indicating if property value can be read out.					
6.41.2.14 unsigned int reserved[8]					
Reserved for future use.					
6.41.2.15 fc2PropertyType type					
Property info type.					
The documentation for this struct was generated from the following file:					
• FlyCapture2Defs_C.h					
6.42 fc2TriggerMode Struct Reference					

Generated by Doxygen

A camera trigger.

Data Fields

	_	$\overline{}$	$\overline{}$				$\overline{}$	
•	К	()	()	1 (n	าเ		Ħ

Flag controlling on/off.

· unsigned int polarity

Polarity value.

• unsigned int source

Source value.

• unsigned int mode

Mode value.

• unsigned int parameter

Parameter value.

• unsigned int reserved [8]

Reserved for future use.

6.42.1 Detailed Description

A camera trigger.

6.42.2 Field Documentation

6.42.2.1 unsigned int mode

Mode value.

6.42.2.2 BOOL onOff

Flag controlling on/off.

6.42.2.3 unsigned int parameter

Parameter value.

6.42.2.4 unsigned int polarity

Polarity value.

6.42.2.5 unsigned int reserved[8]

Reserved for future use.

6.42.2.6 unsigned int source

Source value.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.43 fc2TriggerModeInfo Struct Reference

Information about a camera trigger property.

Data Fields

• BOOL present

Presence of trigger mode.

BOOL readOutSupported

Flag indicating if trigger value can be read out.

BOOL onOffSupported

Flag indicating if on/off is supported.

BOOL polaritySupported

Flag indicating if polarity is supported.

BOOL valueReadable

Flag indicating if the value is readable.

• unsigned int sourceMask

Source mask.

• BOOL softwareTriggerSupported

Flag indicating if software trigger is supported.

unsigned int modeMask

Mode mask.

• unsigned int reserved [8]

Reserved for future use.

6.43.1 Detailed Description

Information about a camera trigger property.

6.43.2 Field Documentation

6.43.2.1 unsigned int modeMask

Mode mask.

6.43.2.2 BOOL onOffSupported Flag indicating if on/off is supported. 6.43.2.3 BOOL polaritySupported Flag indicating if polarity is supported. 6.43.2.4 BOOL present Presence of trigger mode. 6.43.2.5 BOOL readOutSupported Flag indicating if trigger value can be read out. 6.43.2.6 unsigned int reserved[8] Reserved for future use. 6.43.2.7 BOOL softwareTriggerSupported Flag indicating if software trigger is supported. 6.43.2.8 unsigned int sourceMask Source mask.

6.43.2.9 BOOL valueReadable

Flag indicating if the value is readable.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

6.44 fc2Version Struct Reference

The current version of the library.

Data Fields

- · unsigned int major
 - Major version number.
- unsigned int minor
 - Minor version number.
- unsigned int type
 - Type version number.
- · unsigned int build
 - Build version number.

6.44.1 Detailed Description

The current version of the library.

6.44.2 Field Documentation

6.44.2.1 unsigned int build

Build version number.

6.44.2.2 unsigned int major

Major version number.

6.44.2.3 unsigned int minor

Minor version number.

6.44.2.4 unsigned int type

Type version number.

The documentation for this struct was generated from the following file:

• FlyCapture2Defs_C.h

Chapter 7

File Documentation

7.1 FlyCapture2_C.h File Reference

Include dependency graph for FlyCapture2_C.h:

7.2 FlyCapture2Defs_C.h File Reference

Include dependency graph for FlyCapture2Defs_C.h: This graph shows which files directly or indirectly include this file:

Data Structures

• struct fc2PGRGuid

A GUID to the camera.

- struct fc2lmage
- struct fc2SystemInfo

Description of the system.

struct fc2Version

The current version of the library.

struct fc2IPAddress

IPv4 address.

struct fc2MACAddress

MAC address.

• struct fc2GigEProperty

A GigE property.

· struct fc2GigEStreamChannel

Information about a single GigE stream channel.

struct fc2GigEConfig

Configuration for a GigE camera.

• struct fc2GigEImageSettingsInfo

Format 7 information for a single mode.

• struct fc2GigEImageSettings

Image settings for a GigE camera.

struct fc2Format7ImageSettings

Format 7 image settings.

struct fc2Format7Info

Format 7 information for a single mode.

• struct fc2Format7PacketInfo

Format 7 packet information.

· struct fc2Config

Configuration for a camera.

· struct fc2TriggerDelayInfo

Information about a specific camera property.

struct fc2TriggerDelay

A specific camera property.

struct fc2TriggerModeInfo

Information about a camera trigger property.

• struct fc2TriggerMode

A camera trigger.

struct fc2StrobeInfo

A camera strobe property.

struct fc2StrobeControl

A camera strobe.

struct fc2TimeStamp

Timestamp information.

struct fc2ConfigROM

Camera configuration ROM.

· struct fc2CameraInfo

Camera information.

• struct fc2EmbeddedImageInfoProperty

Properties of a single embedded image info property.

• struct fc2EmbeddedImageInfo

Properties of the possible embedded image information.

• struct fc2ImageMetadata

Metadata related to an image.

• struct fc2LUTData

Information about the camera's look up table.

struct fc2CameraStats

Camera diagnostic information.

• struct fc2PNGOption

Options for saving PNG images.

struct fc2PPMOption

Options for saving PPM images.

struct fc2PGMOption

Options for saving PGM images.

struct fc2TIFFOption

Options for saving TIFF images.

• struct fc2JPEGOption

Options for saving JPEG image.

• struct fc2JPG2Option

Options for saving JPEG2000 image.

• struct fc2BMPOption

Options for saving Bitmap image.

• struct fc2MJPGOption

Options for saving MJPG files.

• struct fc2H264Option

Options for saving H264 files.

• struct fc2AVIOption

Options for saving AVI files.

• struct fc2EventOptions

Options for enabling device event registration.

• struct fc2EventCallbackData

Macros

- #define FALSE 0
- #define TRUE 1
- #define FULL_32BIT_VALUE 0x7FFFFFF
- #define MAX_STRING_LENGTH 512

Typedefs

- · typedef int BOOL
- typedef void * fc2Context

A context to the FlyCapture2 C library.

typedef void * fc2GuiContext

A context to the FlyCapture2 C GUI library.

typedef void * fc2lmagelmpl

An internal pointer used in the fc2lmage structure.

typedef void * fc2AVIContext

A context referring to the AVI recorder object.

typedef void * fc2ImageStatisticsContext

A context referring to the ImageStatistics object.

• typedef void * fc2TopologyNodeContext

A context referring to the TopologyNode object.

- typedef void * fc2CallbackHandle
- typedef void(* fc2BusEventCallback) (void *pParameter, unsigned int serialNumber)
- typedef void(* fc2ImageEventCallback) (fc2Image *image, void *pCallbackData)
- typedef void(* fc2AsyncCommandCallback) (fc2Error retError, void *pUserData)
- typedef void(* fc2CameraEventCallback) (void *pCallbackData)

Enumerations

```
enum fc2Error {
 FC2 ERROR UNDEFINED = -1,
 FC2 ERROR OK,
 FC2_ERROR_FAILED,
 FC2 ERROR NOT IMPLEMENTED,
 FC2 ERROR FAILED BUS MASTER CONNECTION,
 FC2 ERROR NOT CONNECTED,
 FC2_ERROR_INIT_FAILED,
 FC2_ERROR_NOT_INTITIALIZED,
 FC2 ERROR INVALID PARAMETER,
 FC2 ERROR INVALID SETTINGS,
 FC2 ERROR INVALID BUS MANAGER,
 FC2 ERROR MEMORY ALLOCATION FAILED,
 FC2 ERROR LOW LEVEL FAILURE,
 FC2 ERROR NOT FOUND,
 FC2_ERROR_FAILED_GUID,
 FC2_ERROR_INVALID_PACKET_SIZE,
 FC2 ERROR INVALID MODE,
 FC2_ERROR_NOT_IN_FORMAT7,
 FC2_ERROR_NOT_SUPPORTED,
 FC2_ERROR_TIMEOUT,
 FC2 ERROR BUS MASTER FAILED,
 FC2 ERROR INVALID GENERATION,
 FC2 ERROR LUT FAILED,
 FC2 ERROR IIDC FAILED,
 FC2 ERROR STROBE FAILED.
 FC2_ERROR_TRIGGER_FAILED,
 FC2 ERROR PROPERTY FAILED,
 FC2 ERROR PROPERTY NOT PRESENT,
 FC2 ERROR REGISTER FAILED,
 FC2_ERROR_READ_REGISTER_FAILED,
 FC2_ERROR_WRITE_REGISTER_FAILED,
 FC2 ERROR ISOCH FAILED,
 FC2 ERROR ISOCH ALREADY STARTED,
 FC2_ERROR_ISOCH_NOT_STARTED,
 FC2 ERROR ISOCH START FAILED,
 FC2 ERROR ISOCH RETRIEVE BUFFER FAILED,
 FC2 ERROR ISOCH STOP FAILED,
 FC2_ERROR_ISOCH_SYNC_FAILED,
 FC2_ERROR_ISOCH_BANDWIDTH_EXCEEDED,
 FC2 ERROR IMAGE CONVERSION FAILED,
 FC2_ERROR_IMAGE_LIBRARY_FAILURE,
 FC2_ERROR_BUFFER_TOO_SMALL,
 FC2 ERROR IMAGE CONSISTENCY ERROR.
 FC2 ERROR INCOMPATIBLE DRIVER.
 FC2 ERROR FORCE 32BITS = FULL 32BIT VALUE }
    The error types returned by functions.

    enum fc2BusCallbackType {

 FC2_BUS_RESET,
 FC2 ARRIVAL,
 FC2 REMOVAL,
 FC2 CALLBACK TYPE FORCE 32BITS = FULL 32BIT VALUE }
    The type of bus callback to register a callback function for.
enum fc2GrabMode {
 FC2 DROP FRAMES,
 FC2_BUFFER_FRAMES,
 FC2_UNSPECIFIED_GRAB_MODE,
```

```
FC2_GRAB_MODE_FORCE_32BITS = FULL_32BIT_VALUE }
    The grab strategy employed during image transfer.
enum fc2GrabTimeout {
 FC2 TIMEOUT NONE = 0,
 FC2 TIMEOUT INFINITE = -1,
 FC2_TIMEOUT_UNSPECIFIED = -2,
 FC2_GRAB_TIMEOUT_FORCE_32BITS = FULL_32BIT_VALUE }
    Timeout options for grabbing images.

    enum fc2BandwidthAllocation {

 FC2 BANDWIDTH ALLOCATION OFF = 0.
 FC2 BANDWIDTH ALLOCATION ON = 1,
 FC2 BANDWIDTH ALLOCATION UNSUPPORTED = 2,
 FC2_BANDWIDTH_ALLOCATION_UNSPECIFIED = 3,
 FC2_BANDWIDTH_ALLOCATION_FORCE_32BITS = FULL_32BIT_VALUE }
    Bandwidth allocation options for 1394 devices.
enum fc2InterfaceType {
 FC2 INTERFACE IEEE1394,
 FC2 INTERFACE USB 2,
 FC2 INTERFACE USB 3,
 FC2 INTERFACE GIGE,
 FC2_INTERFACE_UNKNOWN,
 FC2_INTERFACE_TYPE_FORCE_32BITS = FULL_32BIT_VALUE }
    Interfaces that a camera may use to communicate with a host.

    enum fc2PropertyType {

 FC2 BRIGHTNESS,
 FC2 AUTO_EXPOSURE,
 FC2_SHARPNESS,
 FC2_WHITE_BALANCE,
 FC2 HUE,
 FC2_SATURATION,
 FC2_GAMMA,
 FC2_IRIS,
 FC2 FOCUS.
 FC2 ZOOM,
 FC2_PAN,
 FC2_TILT,
 FC2 SHUTTER,
 FC2 GAIN,
 FC2_TRIGGER_MODE,
 FC2_TRIGGER_DELAY,
 FC2_FRAME_RATE,
 FC2_TEMPERATURE,
 FC2_UNSPECIFIED_PROPERTY_TYPE,
 FC2 PROPERTY TYPE FORCE 32BITS = FULL 32BIT VALUE }
    Camera properties.
enum fc2FrameRate {
 FC2 FRAMERATE 1 875,
 FC2_FRAMERATE_3_75,
 FC2_FRAMERATE_7_5,
 FC2 FRAMERATE 15,
 FC2 FRAMERATE 30,
 FC2 FRAMERATE 60,
 FC2 FRAMERATE 120,
 FC2 FRAMERATE 240,
 FC2 FRAMERATE FORMAT7,
 FC2_NUM_FRAMERATES,
 FC2_FRAMERATE_FORCE_32BITS = FULL_32BIT_VALUE }
```

Frame rates in frames per second.

```
enum fc2VideoMode {
 FC2 VIDEOMODE 160x120YUV444,
 FC2 VIDEOMODE 320x240YUV422,
 FC2_VIDEOMODE_640x480YUV411,
 FC2_VIDEOMODE_640x480YUV422,
 FC2 VIDEOMODE 640x480RGB,
 FC2_VIDEOMODE_640x480Y8,
 FC2_VIDEOMODE_640x480Y16,
 FC2_VIDEOMODE_800x600YUV422,
 FC2_VIDEOMODE_800x600RGB,
 FC2_VIDEOMODE_800x600Y8,
 FC2_VIDEOMODE_800x600Y16,
 FC2_VIDEOMODE_1024x768YUV422,
 FC2 VIDEOMODE 1024x768RGB,
 FC2_VIDEOMODE_1024x768Y8,
 FC2_VIDEOMODE_1024x768Y16,
 FC2_VIDEOMODE_1280x960YUV422,
 FC2 VIDEOMODE 1280x960RGB,
 FC2_VIDEOMODE_1280x960Y8,
 FC2_VIDEOMODE_1280x960Y16,
 FC2_VIDEOMODE_1600x1200YUV422,
 FC2_VIDEOMODE_1600x1200RGB,
 FC2_VIDEOMODE_1600x1200Y8,
 FC2_VIDEOMODE_1600x1200Y16,
 FC2 VIDEOMODE FORMAT7,
 FC2 NUM VIDEOMODES,
 FC2_VIDEOMODE_FORCE_32BITS = FULL_32BIT_VALUE }
```

DCAM video modes.

• enum fc2Mode {

```
FC2\_MODE\_0 = 0,
 FC2 MODE 1,
 FC2 MODE 2,
 FC2_MODE_3,
 FC2_MODE_4,
 FC2 MODE 5,
 FC2 MODE_6,
 FC2 MODE 7,
 FC2 MODE 8,
 FC2 MODE 9,
 FC2_MODE_10,
 FC2_MODE_11,
 FC2_MODE_12,
 FC2 MODE 13,
 FC2_MODE_14,
 FC2_MODE_15,
 FC2 MODE 16,
 FC2_MODE_17,
 FC2_MODE_18,
 FC2 MODE 19,
 FC2 MODE 20,
 FC2 MODE 21,
 FC2_MODE_22,
 FC2_MODE_23,
 FC2 MODE 24,
 FC2 MODE 25,
 FC2_MODE_26,
 FC2 MODE 27,
 FC2 MODE 28.
 FC2 MODE_29,
 FC2_MODE_30,
 FC2_MODE_31,
 FC2 NUM MODES,
 FC2_MODE_FORCE_32BITS = FULL_32BIT_VALUE }
    Camera modes for DCAM formats as well as Format7.
enum fc2PixelFormat {
 FC2_PIXEL_FORMAT_MONO8 = 0x80000000,
 FC2_PIXEL_FORMAT_411YUV8 = 0x40000000,
 FC2_PIXEL_FORMAT_422YUV8 = 0x200000000,
 FC2 PIXEL FORMAT 444YUV8 = 0x10000000,
 FC2 PIXEL FORMAT RGB8 = 0x08000000,
 FC2 PIXEL FORMAT MONO16 = 0x04000000,
 FC2 PIXEL FORMAT RGB16 = 0x02000000,
 FC2_PIXEL_FORMAT_S_MONO16 = 0x01000000,
 FC2_PIXEL_FORMAT_S_RGB16 = 0x00800000,
 FC2_PIXEL_FORMAT_RAW8 = 0x00400000,
 FC2_PIXEL_FORMAT_RAW16 = 0x00200000,
 FC2 PIXEL FORMAT MONO12 = 0 \times 00100000,
 FC2_PIXEL_FORMAT_RAW12 = 0x00080000,
 FC2_PIXEL_FORMAT_BGR = 0x80000008,
 FC2 PIXEL FORMAT BGRU = 0x40000008,
 FC2_PIXEL_FORMAT_RGB = FC2_PIXEL_FORMAT_RGB8,
 FC2_PIXEL_FORMAT_RGBU = 0x40000002,
 FC2 PIXEL FORMAT BGR16 = 0x02000001,
 FC2 PIXEL FORMAT BGRU16 = 0x02000002,
 FC2 PIXEL FORMAT 422YUV8 JPEG = 0x40000001,
 FC2_NUM_PIXEL_FORMATS = 20,
 FC2_UNSPECIFIED_PIXEL_FORMAT = 0 }
```

```
Pixel formats available for Format7 modes.

    enum fc2BusSpeed {

 FC2 BUSSPEED S100,
 FC2_BUSSPEED_S200,
 FC2_BUSSPEED_S400,
 FC2 BUSSPEED S480,
 FC2_BUSSPEED_S800,
 FC2_BUSSPEED_S1600,
 FC2 BUSSPEED S3200,
 FC2 BUSSPEED S5000,
 FC2_BUSSPEED_10BASE_T,
 FC2_BUSSPEED_100BASE_T,
 FC2 BUSSPEED 1000BASE T,
 FC2 BUSSPEED 10000BASE T,
 FC2_BUSSPEED_S_FASTEST,
 FC2_BUSSPEED_ANY,
 FC2 BUSSPEED SPEED UNKNOWN = -1,
 FC2 BUSSPEED FORCE 32BITS = FULL 32BIT VALUE }
    Bus speeds.

    enum fc2PCleBusSpeed {

 FC2 PCIE BUSSPEED 2 5,
 FC2_PCIE_BUSSPEED_5_0,
 FC2_PCIE_BUSSPEED_UNKNOWN = -1,
 FC2_PCIE_BUSSPEED_FORCE_32BITS = FULL_32BIT_VALUE }
enum fc2DriverType {
 FC2_DRIVER_1394_CAM,
 FC2_DRIVER_1394_PRO,
 FC2 DRIVER 1394 JUJU,
 FC2_DRIVER_1394_VIDEO1394,
 FC2_DRIVER_1394_RAW1394,
 FC2 DRIVER USB NONE,
 FC2 DRIVER USB CAM,
 FC2 DRIVER USB3 PRO,
 FC2_DRIVER_GIGE_NONE,
 FC2 DRIVER GIGE FILTER,
 FC2 DRIVER_GIGE_PRO,
 FC2 DRIVER GIGE LWF,
 FC2 DRIVER UNKNOWN = -1,
 FC2 DRIVER FORCE 32BITS = FULL 32BIT VALUE }
    Types of low level drivers that FlyCapture uses.
• enum fc2ColorProcessingAlgorithm {
 FC2_DEFAULT,
 FC2 NO COLOR PROCESSING,
 FC2 NEAREST NEIGHBOR FAST.
 FC2 EDGE SENSING,
 FC2 HQ LINEAR,
 FC2 RIGOROUS,
 FC2 IPP,
 FC2 DIRECTIONAL,
 FC2_COLOR_PROCESSING_ALGORITHM_FORCE_32BITS = FULL_32BIT_VALUE }
    Color processing algorithms.

    enum fc2BayerTileFormat {

 FC2 BT NONE,
 FC2 BT RGGB,
 FC2 BT GRBG,
 FC2 BT GBRG,
 FC2 BT BGGR,
 FC2_BT_FORCE_32BITS = FULL_32BIT_VALUE }
```

```
Bayer tile formats.
enum fc2lmageFileFormat {
 FC2 FROM FILE EXT = -1,
 FC2 PGM,
 FC2 PPM,
 FC2 BMP,
 FC2_JPEG,
 FC2 JPEG2000,
 FC2 TIFF,
 FC2 PNG,
 FC2 RAW,
 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS = FULL_32BIT_VALUE }
    File formats to be used for saving images to disk.

    enum fc2GigEPropertyType {

 FC2 HEARTBEAT,
 FC2_HEARTBEAT_TIMEOUT,
 PACKET SIZE,
 PACKET_DELAY }
    Possible properties that can be queried from the camera.
enum fc2StatisticsChannel {
 FC2 STATISTICS GREY,
 FC2 STATISTICS RED,
 FC2 STATISTICS GREEN,
 FC2_STATISTICS_BLUE,
 FC2_STATISTICS_HUE,
 FC2 STATISTICS SATURATION,
 FC2 STATISTICS LIGHTNESS,
 FC2_STATISTICS_FORCE_32BITS = FULL_32BIT_VALUE }
    Channels that allow statistics to be calculated.
enum fc2OSType {
 FC2 WINDOWS X86,
 FC2 WINDOWS X64,
 FC2_LINUX_X86,
 FC2 LINUX X64,
 FC2 MAC.
 FC2_UNKNOWN OS.
 FC2_OSTYPE_FORCE_32BITS = FULL_32BIT_VALUE }
    Possible operating systems.
enum fc2ByteOrder {
 FC2 BYTE ORDER LITTLE ENDIAN,
 FC2_BYTE_ORDER_BIG_ENDIAN,
 FC2_BYTE_ORDER_FORCE_32BITS = FULL_32BIT_VALUE }
    Possible byte orders.
enum fc2PortType {
 NOT CONNECTED = 1,
 CONNECTED_TO_PARENT,
 CONNECTED_TO_CHILD }
    Possible states of a port on a node.
enum fc2NodeType {
 COMPUTER,
 BUS,
 CAMERA,
 NODE }
    Type of node.
```

```
    enum fc2TIFFCompressionMethod {

     FC2\_TIFF\_NONE = 1,
     FC2_TIFF_PACKBITS,
     FC2_TIFF_DEFLATE,
     FC2_TIFF_ADOBE_DEFLATE,
     FC2 TIFF CCITTFAX3,
     FC2_TIFF_CCITTFAX4,
     FC2_TIFF_LZW,
     FC2_TIFF_JPEG }
7.2.1 Enumeration Type Documentation
7.2.1.1 enum fc2ByteOrder
Possible byte orders.
Enumerator
     FC2_BYTE_ORDER_LITTLE_ENDIAN
     FC2_BYTE_ORDER_BIG_ENDIAN
     FC2_BYTE_ORDER_FORCE_32BITS
7.2.1.2 enum fc2NodeType
Type of node.
Enumerator
     COMPUTER
     BUS
     CAMERA
     NODE
7.2.1.3 enum fc2OSType
Possible operating systems.
Enumerator
     FC2 WINDOWS X86 All Windows 32-bit variants.
     FC2_WINDOWS_X64 All Windows 64-bit variants.
     FC2_LINUX_X86 All Linux 32-bit variants.
     FC2_LINUX_X64 All Linux 32-bit variants.
     FC2_MAC Mac OSX.
     FC2_UNKNOWN_OS Unknown operating system.
```

FC2_OSTYPE_FORCE_32BITS

7.2.1.4 enum fc2PortType

Possible states of a port on a node.

Enumerator

NOT_CONNECTED
CONNECTED_TO_PARENT
CONNECTED_TO_CHILD

7.2.1.5 enum fc2StatisticsChannel

Channels that allow statistics to be calculated.

Enumerator

FC2_STATISTICS_GREY
FC2_STATISTICS_RED
FC2_STATISTICS_GREEN
FC2_STATISTICS_BLUE
FC2_STATISTICS_HUE
FC2_STATISTICS_SATURATION
FC2_STATISTICS_LIGHTNESS
FC2_STATISTICS_FORCE_32BITS

7.3 FlyCapture2GUI_C.h File Reference

Include dependency graph for FlyCapture2GUI C.h:

Functions

FLYCAPTURE2_C_API fc2Error fc2CreateGUIContext (fc2GuiContext *pContext)

Create a GUI context.

• FLYCAPTURE2 C API fc2Error fc2DestroyGUIContext (fc2GuiContext context)

Destroy a GUI context.

FLYCAPTURE2_C_API void fc2GUIConnect (fc2GuiContext context, fc2Context cameraContext)

Connect GUI context to a camera context.

• FLYCAPTURE2_C_API void fc2GUIDisconnect (fc2GuiContext context)

Disconnect GUI context from camera.

• FLYCAPTURE2_C_API void fc2Disonnect (fc2GuiContext context) __attribute__((deprecated))

Disconnect GUI context from camera.

• FLYCAPTURE2_C_API void fc2Show (fc2GuiContext context)

Show the GUI.

• FLYCAPTURE2_C_API void fc2Hide (fc2GuiContext context)

Hide the GUI.

• FLYCAPTURE2_C_API BOOL fc2IsVisible (fc2GuiContext context)

Check if the GUI is visible.

• FLYCAPTURE2_C_API void fc2ShowModal (fc2GuiContext context, BOOL *pOkSelected, fc2PGRGuid *guidArray, unsigned int *size)

Show the camera selection dialog.

7.3.1 Function Documentation

7.3.1.1 FLYCAPTURE2_C_API fc2Error fc2CreateGUIContext (fc2GuiContext * pContext)

Create a GUI context.

Parameters

pContext	Pointer to context to be created.
----------	-----------------------------------

Returns

An Error indicating the success or failure of the function.

7.3.1.2 FLYCAPTURE2_C_API fc2Error fc2DestroyGUIContext (fc2GuiContext context)

Destroy a GUI context.

Parameters

context	Context to be destroyed.
---------	--------------------------

Returns

An Error indicating the success or failure of the function.

7.3.1.3 FLYCAPTURE2_C_API void fc2Disonnect (fc2GuiContext context)

Disconnect GUI context from camera.

Parameters

۱		0111
۱	context	GUI context to disconnect.

Returns

An Error indicating the success or failure of the function.

Deprecated This method is deprecated and will be removed in a future FlyCapture2 release. Please use fc2GU← IDisconnect instead.

7.3.1.4 FLYCAPTURE2_C_API void fc2GUIConnect (fc2GuiContext context, fc2Context cameraContext)

Connect GUI context to a camera context.

Parameters

context	GUI context to connect.
cameraContext	Camera context to connect.

Returns

An Error indicating the success or failure of the function.

7.3.1.5 FLYCAPTURE2_C_API void fc2GUIDisconnect (fc2GuiContext context)

Disconnect GUI context from camera.

Parameters

context	GUI context to disconnect.
---------	----------------------------

Returns

An Error indicating the success or failure of the function.

7.3.1.6 FLYCAPTURE2_C_API void fc2Hide (fc2GuiContext context)

Hide the GUI.

Parameters

context	Pointer to context to hide.

Returns

An Error indicating the success or failure of the function.

7.3.1.7 FLYCAPTURE2_C_API BOOL fc2lsVisible (fc2GuiContext context)

Check if the GUI is visible.

Parameters

context	Pointer to context to show.

Returns

Whether the GUI is visible.

7.3.1.8 FLYCAPTURE2_C_API void fc2Show (fc2GuiContext context)

Show the GUI.

Parameters

context	Pointer to context to show.
---------	-----------------------------

Returns

An Error indicating the success or failure of the function.

7.3.1.9 FLYCAPTURE2_C_API void fc2ShowModal (fc2GuiContext context, BOOL * pOkSelected, fc2PGRGuid * guidArray, unsigned int * size)

Show the camera selection dialog.

Parameters

context	Pointer to context to show.
pOkSelected	Whether Ok (true) or Cancel (false) was clicked.
guidArray	Array of PGRGuids containing the selected cameras.
size	Size of PGRGuid array.

7.4 FlyCapture2Internal_C.h File Reference

Include dependency graph for FlyCapture2Internal_C.h:

Data Structures

- struct fc2InternalContext
- struct fc2InternalGuiContext
- struct fc2InternalImageCallback

Functions

- bool IsContextValid (fc2Context context)
- bool IsGuiContextValid (fc2GuiContext context)
- void SyncCppImageToStruct (fc2Image *pImage)

7.4.1 Function Documentation

```
7.4.1.1 bool lsContextValid (fc2Context context) [inline]
```

7.4.1.2 bool lsGuiContextValid (fc2GuiContext context) [inline]

7.4.1.3 void SyncCpplmageToStruct (fc2Image * plmage) [inline]

7.5 FlyCapture2Platform_C.h File Reference

This graph shows which files directly or indirectly include this file:

Macros

- #define FLYCAPTURE2_C_API
- #define FLYCAPTURE2_C_CALL_CONVEN

7.5.1 Macro Definition Documentation

7.5.1.1 #define FLYCAPTURE2_C_API

7.5.1.2 #define FLYCAPTURE2_C_CALL_CONVEN

7.6 FlyCapture2Private_C.h File Reference

Include dependency graph for FlyCapture2Private_C.h:

Functions

• FLYCAPTURE2_C_API void * GetInternal (unsigned int index)

7.6.1 Function Documentation

7.6.1.1 FLYCAPTURE2_C_API void* GetInternal (unsigned int index)

7.7 MultiSyncLibrary_C.h File Reference

Include dependency graph for MultiSyncLibrary_C.h:

Functions

MULTISYNCLIBRARY_C_API syncError syncCreateContext (syncContext *pContext)

Create a Sync context for MultiSync Library.

MULTISYNCLIBRARY_C_API syncError syncDestroyContext (syncContext context)

Destory the sync context.

MULTISYNCLIBRARY_C_API syncError syncStart (syncContext context)

Start the sync progress.

MULTISYNCLIBRARY_C_API syncError syncStop (syncContext context)

Stop the sync progress.

MULTISYNCLIBRARY_C_API syncError syncRescanMasterTimingBus (syncContext context)

Scan newly connected or removed timing bus (for corss-PC syncing only)

MULTISYNCLIBRARY_C_API syncMessage syncGetStatus (syncContext context)

Start the sync progress.

MULTISYNCLIBRARY C API double syncGetTimeSinceSynced (syncContext context)

Time since sync started.

MULTISYNCLIBRARY C API BOOL syncIsTimingBusConnected (syncContext context)

Whether syncing across PCs.

MULTISYNCLIBRARY C API BOOL syncEnableCrossPCSynchronization (syncContext context)

Enable across pc synchronization support.

MULTISYNCLIBRARY_C_API BOOL syncDisableCrossPCSynchronization (syncContext context)

Disable across pc synchronization support.

MULTISYNCLIBRARY C API BOOL syncQueryCrossPCSynchronizationSetting (syncContext context)

Query cross pc synchronizaion support status.

7.7.1 Function Documentation

7.7.1.1 MULTISYNCLIBRARY C API syncError syncCreateContext (syncContext * pContext)

Create a Sync context for MultiSync Library.

This call must be made before any other calls that use a context will succeed.

Parameters

l	pContext	A pointer to the syncContext to be created.

Returns

A syncError indicating the success or failure of the function.

7.7.1.2 MULTISYNCLIBRARY_C_API syncError syncDestroyContext (syncContext context)

Destory the sync context.

This must be called when the user is finished with the context in order to prevent memory leaks.

Parameters

context	The syncContext to be destoryed.
---------	----------------------------------

Returns

A syncError indicating the success or failure of the function.

7.7.1.3 MULTISYNCLIBRARY_C_API BOOL syncDisableCrossPCSynchronization (syncContext context)

Disable across pc synchronization support.

Parameters

context	The syncContext to be used.
---------	-----------------------------

Returns

True if operation was successful

7.7.1.4 MULTISYNCLIBRARY_C_API BOOL syncEnableCrossPCSynchronization (syncContext context)

Enable across pc synchronization support.

Parameters

context	The syncContext to be used.
---------	-----------------------------

Returns

True if operation was successful

7.7.1.5 MULTISYNCLIBRARY_C_API syncMessage syncGetStatus (syncContext context)

Start the sync progress.

Parameters

Returns

A syncMessage indicating the sync status.

7.7.1.6 MULTISYNCLIBRARY_C_API double syncGetTimeSinceSynced (syncContext context)

Time since sync started.

Parameters

context	The syncContext to be used.
000,	ino of noodintont to be decar

Returns

Time sinced synced.

7.7.1.7 MULTISYNCLIBRARY_C_API BOOL synclsTimingBusConnected (syncContext context)

Whether syncing across PCs.

Parameters

context	The syncContext to be used.
---------	-----------------------------

Returns

True if its syncing across PC

7.7.1.8 MULTISYNCLIBRARY_C_API BOOL syncQueryCrossPCSynchronizationSetting (syncContext context)

Query cross pc synchronizaion support status.

Parameters

context	The syncContext to be used.
---------	-----------------------------

Returns

True if cross pc synchronization was supported

7.7.1.9 MULTISYNCLIBRARY_C_API syncError syncRescanMasterTimingBus (syncContext context)

Scan newly connected or removed timing bus (for corss-PC syncing only)

Parameters

context	The syncContext to be used.
Context	The syncooniext to be used.

Returns

A syncError indicating the success or failure of the function.

7.7.1.10 MULTISYNCLIBRARY_C_API syncError syncStart (syncContext context)

Start the sync progress.

Parameters

context	The syncContext to be used.
---------	-----------------------------

Returns

A syncError indicating the success or failure of the function.

7.7.1.11 MULTISYNCLIBRARY_C_API syncError syncStop (syncContext context)

Stop the sync progress.

Parameters

context	The syncContext to be used.
---------	-----------------------------

Returns

A syncError indicating the success or failure of the function.

7.8 MultiSyncLibraryDefs_C.h File Reference

Include dependency graph for MultiSyncLibraryDefs_C.h: This graph shows which files directly or indirectly include this file:

Macros

- #define FALSE 0
- #define TRUE 1
- #define FULL 32BIT VALUE 0x7FFFFFF
- #define MAX_STRING_LENGTH 512

Typedefs

- · typedef int BOOL
- typedef void * syncContext

A context to the MultiSync C library.

Enumerations

```
enum syncError {
 SYNC\_ERROR\_OK = 0,
 SYNC ERROR FAILED,
 SYNC ERROR ALREADY STARTED,
 SYNC_ERROR_ALREADY_STOPPED,
 SYNC_ERROR_CONTEXT_NOT_INITIALIZED,
 SYNC_ERROR_UNKNOWN_ERROR }
• enum syncMessage {
 SYNC MESSAGE OK = 0,
 SYNC MESSAGE FAILED,
 SYNC MESSAGE STARTED,
 SYNC_MESSAGE_STOPPED,
 SYNC_MESSAGE_SYNCING,
 SYNC MESSAGE NOMASTER,
 SYNC_MESSAGE_THREAD_ERROR,
 SYNC_MESSAGE_DEVICE_ERROR,
 SYNC_MESSAGE_NOT_ENOUGH_DEVICES,
 SYNC MESSAGE BUS RESET,
 SYNC_MESSAGE_NOT_INITIALIZED,
 SYNC_MESSAGE_UNKNOWN_ERROR }
```

7.8.1 Macro Definition Documentation

- 7.8.1.1 #define FALSE 0
- 7.8.1.2 #define FULL_32BIT_VALUE 0x7FFFFFF
- 7.8.1.3 #define MAX_STRING_LENGTH 512
- 7.8.1.4 #define TRUE 1
- 7.8.2 Typedef Documentation
- 7.8.2.1 typedef int BOOL
- 7.8.2.2 typedef void* syncContext

A context to the MultiSync C library.

It must be created before performing any calls to the library.

7.8.3 Enumeration Type Documentation

7.8.3.1 enum syncError

Enumerator

SYNC_ERROR_OK
SYNC_ERROR_FAILED
SYNC_ERROR_ALREADY_STARTED
SYNC_ERROR_ALREADY_STOPPED
SYNC_ERROR_CONTEXT_NOT_INITIALIZED
SYNC_ERROR_UNKNOWN_ERROR

7.8.3.2 enum syncMessage

Enumerator

SYNC_MESSAGE_OK

SYNC_MESSAGE_FAILED

SYNC_MESSAGE_STARTED

SYNC_MESSAGE_STOPPED

SYNC_MESSAGE_SYNCING

SYNC MESSAGE NOMASTER

SYNC_MESSAGE_THREAD_ERROR

SYNC_MESSAGE_DEVICE_ERROR

SYNC_MESSAGE_NOT_ENOUGH_DEVICES

SYNC_MESSAGE_BUS_RESET

SYNC_MESSAGE_NOT_INITIALIZED

SYNC_MESSAGE_UNKNOWN_ERROR

7.9 MultiSyncLibraryPlatform_C.h File Reference

This graph shows which files directly or indirectly include this file:

Macros

- #define MULTISYNCLIBRARY_C_API
- #define MULTISYNCLIBRARY_C_CALL_CONVEN

7.9.1 Macro Definition Documentation

- 7.9.1.1 #define MULTISYNCLIBRARY_C_API
- 7.9.1.2 #define MULTISYNCLIBRARY_C_CALL_CONVEN

Index

AVI Recording Operation, 84	fc2Version, 177
fc2AVIAppend, 84	Bus Manager Operation, 9
fc2AVIClose, 84	fc2DiscoverGigECameras, 10
fc2AVIOpen, 85	fc2FireBusReset, 11
fc2CreateAVI, 85	fc2ForceAllIPAddressesAutomatically, 11
fc2DestroyAVI, 85	fc2ForceIPAddressAutomatically, 11
fc2H264Open, 86	fc2ForceIPAddressToCamera, 11
fc2MJPGOpen, 86	fc2GetCameraFromIPAddress, 12
absControl	fc2GetCameraFromIndex, 12
fc2TriggerDelay, 170	fc2GetCameraFromSerialNumber, 13
absMax	fc2GetCameraSerialNumberFromIndex, 13
fc2TriggerDelayInfo, 172	fc2GetDeviceFromIndex, 13
absMin	fc2GetInterfaceTypeFromGuid, 14
fc2TriggerDelayInfo, 172	fc2GetNumOfCameras, 14
absValSupported	fc2GetNumOfDevices, 14
fc2TriggerDelayInfo, 172	fc2GetTopology, 15
absValue	fc2GetUsbLinkInfo, 15
fc2TriggerDelay, 170	fc2GetUsbPortStatus, 15
applicationIPAddress	fc2lsCameraControlable, 16
fc2CameraInfo, 124	fc2ReadPhyRegister, 16
applicationPort	fc2RegisterCallback, 16
fc2CameraInfo, 124	fc2RescanBus, 17
asyncBusSpeed	fc2UnregisterCallback, 17
fc2Config, 130	fc2WritePhyRegister, 17
autoManualMode	busNumber
fc2TriggerDelay, 170	fc2CameraInfo, 124
autoSupported	byteOrder
fc2TriggerDelayInfo, 172	fc2SystemInfo, 166
available	
fc2EmbeddedImageInfoProperty, 136	CAMERA
	FlyCapture2Defs_C.h, 188
BOOL	COMPUTER
MultiSyncLibraryDefs_C.h, 198	FlyCapture2Defs_C.h, 188
TypeDefs, 98	CONNECTED_TO_CHILD
BUS	FlyCapture2Defs_C.h, 189
FlyCapture2Defs_C.h, 188	CONNECTED_TO_PARENT
bandwidthAllocation	FlyCapture2Defs_C.h, 189
fc2Config, 130	cameraCurrents
bayerFormat	fc2CameraStats, 128
fc2Image, 151	cameraPowerUp
bayerTileFormat	fc2CameraStats, 128
fc2CameraInfo, 124	cameraVoltages
binaryFile	fc2CameraStats, 128
fc2PGMOption, 160	ccpStatus
fc2PPMOption, 162	fc2CameraInfo, 124
bitrate	chipldHi
fc2H264Option, 150	fc2ConfigROM, 133
brightness	chipldLo
fc2EmbeddedImageInfo, 135	fc2ConfigROM, 133
build	cols

fc2Image, 151	embeddedGPIOPinState
compression	fc2ImageMetadata, 152
fc2TIFFOption, 167	embeddedGain
compressionLevel	fc2ImageMetadata, 152
fc2PNGOption, 161	embeddedROIPosition
configROM	fc2ImageMetadata, 153
fc2CameraInfo, 124	embeddedShutter
Connection and Image Retrieval, 19	fc2ImageMetadata, 153
fc2Connect, 19	embeddedStrobePattern
fc2Disconnect, 20	fc2ImageMetadata, 153
fc2GetConfiguration, 20	embeddedTimeStamp
fc2RetrieveBuffer, 20	fc2ImageMetadata, 153
fc2SetCallback, 21	embeddedWhiteBalance
fc2SetConfiguration, 21	fc2ImageMetadata, 153
fc2SetUserBuffers, 21	enablePacketResend
fc2StartCapture, 22	fc2GigEConfig, 143
fc2StartCaptureCallback, 22	enabled
fc2StartSyncCapture, 23	fc2LUTData, 157
fc2StartSyncCaptureCallback, 23	Enumerations, 100
fc2StopCapture, 24	FC2_ARRIVAL, 106
fc2WaitForBufferEvent, 24	FC2_AUTO_EXPOSURE, 112
cpuDescription	FC2_BANDWIDTH_ALLOCATION_FORCE_32↔
fc2SystemInfo, 166	BITS, 105
cycleCount	FC2_BANDWIDTH_ALLOCATION_OFF, 105
fc2TimeStamp, 168	FC2 BANDWIDTH ALLOCATION ON, 105
cycleOffset	FC2 BANDWIDTH ALLOCATION UNSPECIFI←
fc2TimeStamp, 168	ED, 105
cycleSeconds	FC2_BANDWIDTH_ALLOCATION_UNSUPPO←
fc2TimeStamp, 168	RTED, 105
DCAM Formata, E1	FC2_BMP, 109
DCAM Formats, 51	FC2_BRIGHTNESS, 112
fc2GetVideoModeAndFrameRate, 51 fc2GetVideoModeAndFrameRateInfo, 51	FC2_BT_BGGR, 105
fc2SetVideoModeAndFrameRate, 52	FC2_BT_FORCE_32BITS, 105
dataSize	FC2_BT_GBRG, 105
fc2Image, 151	FC2_BT_GRBG, 105
defaultGateway	FC2_BT_NONE, 105
fc2CameraInfo, 125	FC2_BT_RGGB, 105
delay	FC2_BUFFER_FRAMES, 109
fc2StrobeControl, 163	FC2_BUS_RESET, 106
destinationIpAddress	FC2_BUSSPEED_10000BASE_T, 106
fc2GigEStreamChannel, 149	FC2_BUSSPEED_1000BASE_T, 106
doNotFragment	FC2_BUSSPEED_100BASE_T, 106
fc2GigEStreamChannel, 149	FC2_BUSSPEED_10BASE_T, 106
driverList	FC2_BUSSPEED_ANY, 106
fc2SystemInfo, 166	FC2_BUSSPEED_FORCE_32BITS, 106
driverName	FC2_BUSSPEED_S100, 106
fc2CameraInfo, 125	FC2_BUSSPEED_S1600, 106
driverType	FC2_BUSSPEED_S200, 106
fc2CameraInfo, 125	FC2_BUSSPEED_S3200, 106
duration	FC2_BUSSPEED_S400, 106
fc2StrobeControl, 163	FC2_BUSSPEED_S480, 106
	FC2_BUSSPEED_S5000, 106
embeddedBrightness	FC2_BUSSPEED_S800, 106
fc2ImageMetadata, 152	FC2_BUSSPEED_S_FASTEST, 106
embeddedExposure	FC2_BUSSPEED_SPEED_UNKNOWN, 106
fc2ImageMetadata, 152	FC2_CALLBACK_TYPE_FORCE_32BITS, 106
embeddedFrameCounter	FC2_COLOR_PROCESSING_ALGORITHM_F↔
fc2ImageMetadata, 152	ORCE_32BITS, 106

FOO DEFAULT 400	FOR EDDOR NOT CURRORTED 107
FC2_DEFAULT, 106	FC2_ERROR_NOT_SUPPORTED, 107
FC2_DIRECTIONAL, 106	FC2_ERROR_OK, 107
FC2_DRIVER_1394_CAM, 107	FC2_ERROR_PROPERTY_FAILED, 108
FC2_DRIVER_1394_JUJU, 107	FC2_ERROR_PROPERTY_NOT_PRESENT, 108
FC2_DRIVER_1394_PRO, 107	FC2_ERROR_READ_REGISTER_FAILED, 108
FC2_DRIVER_1394_RAW1394, 107	FC2_ERROR_REGISTER_FAILED, 108
FC2_DRIVER_1394_VIDEO1394, 107	FC2_ERROR_STROBE_FAILED, 108
FC2_DRIVER_FORCE_32BITS, 107	FC2_ERROR_TIMEOUT, 107
FC2_DRIVER_GIGE_FILTER, 107	FC2_ERROR_TRIGGER_FAILED, 108
FC2_DRIVER_GIGE_LWF, 107	FC2_ERROR_UNDEFINED, 107
FC2_DRIVER_GIGE_NONE, 107	FC2_ERROR_WRITE_REGISTER_FAILED, 108
FC2_DRIVER_GIGE_PRO, 107	FC2_FOCUS, 112
FC2_DRIVER_UNKNOWN, 107	FC2_FRAME_RATE, 112
FC2_DRIVER_USB3_PRO, 107	FC2_FRAMERATE_120, 108
FC2_DRIVER_USB_CAM, 107	FC2_FRAMERATE_15, 108
FC2_DRIVER_USB_NONE, 107	FC2_FRAMERATE_1_875, 108
FC2_DROP_FRAMES, 109	FC2_FRAMERATE_240, 108
FC2_EDGE_SENSING, 106	FC2_FRAMERATE_30, 108
FC2_ERROR_BUFFER_TOO_SMALL, 108	FC2_FRAMERATE_3_75, 108
FC2_ERROR_BUS_MASTER_FAILED, 108	FC2_FRAMERATE_60, 108
FC2_ERROR_FAILED_BUS_MASTER_CONN↔	FC2_FRAMERATE_7_5, 108
ECTION, 107	FC2_FRAMERATE_FORCE_32BITS, 108
FC2_ERROR_FAILED_GUID, 107	FC2_FRAMERATE_FORMAT7, 108
FC2_ERROR_FAILED, 107	FC2_FROM_FILE_EXT, 109
FC2_ERROR_FORCE_32BITS, 108	FC2_GAIN, 112
FC2_ERROR_IIDC_FAILED, 108	FC2_GAMMA, 112
FC2_ERROR_IMAGE_CONSISTENCY_ERROR,	FC2_GRAB_MODE_FORCE_32BITS, 109
108	FC2_GRAB_TIMEOUT_FORCE_32BITS, 109
FC2_ERROR_IMAGE_CONVERSION_FAILED,	FC2_HQ_LINEAR, 106
108	FC2_HUE, 112
FC2_ERROR_IMAGE_LIBRARY_FAILURE, 108	FC2_IMAGE_FILE_FORMAT_FORCE_32BITS,
FC2_ERROR_INCOMPATIBLE_DRIVER, 108	109
FC2_ERROR_INIT_FAILED, 107	FC2_INTERFACE_GIGE, 110
FC2_ERROR_INVALID_BUS_MANAGER, 107	FC2_INTERFACE_IEEE1394, 110
FC2_ERROR_INVALID_GENERATION, 108	FC2_INTERFACE_TYPE_FORCE_32BITS, 110
FC2_ERROR_INVALID_MODE, 107	FC2_INTERFACE_UNKNOWN, 110
FC2_ERROR_INVALID_PACKET_SIZE, 107	FC2_INTERFACE_USB_2, 110
FC2_ERROR_INVALID_PARAMETER, 107	FC2_INTERFACE_USB_3, 110
FC2_ERROR_INVALID_SETTINGS, 107	FC2_IPP, 106
FC2_ERROR_ISOCH_ALREADY_STARTED, 108	FC2_IRIS, 112
FC2_ERROR_ISOCH_BANDWIDTH_EXCEED↔	FC2_JPEG2000, 109
ED, 108	FC2_JPEG, 109
FC2_ERROR_ISOCH_FAILED, 108	FC2_MODE_0, 110
FC2_ERROR_ISOCH_NOT_STARTED, 108	FC2_MODE_1, 110
FC2_ERROR_ISOCH_RETRIEVE_BUFFER_F↔	FC2_MODE_10, 110
AILED, 108	FC2_MODE_11, 110
FC2_ERROR_ISOCH_START_FAILED, 108	FC2_MODE_12, 110
FC2_ERROR_ISOCH_STOP_FAILED, 108	FC2_MODE_13, 110
FC2_ERROR_ISOCH_SYNC_FAILED, 108	FC2_MODE_14, 110
FC2_ERROR_LOW_LEVEL_FAILURE, 107	FC2_MODE_15, 110
FC2_ERROR_LUT_FAILED, 108	FC2_MODE_16, 110
FC2_ERROR_MEMORY_ALLOCATION_FAILED,	FC2_MODE_17, 110
107	FC2_MODE_18, 110
FC2_ERROR_NOT_CONNECTED, 107	FC2_MODE_19, 110
FC2_ERROR_NOT_FOUND, 107	FC2_MODE_2, 110
FC2_ERROR_NOT_IMPLEMENTED, 107	FC2_MODE_20, 110
FC2_ERROR_NOT_IN_FORMAT7, 107	FC2_MODE_21, 110
FC2_ERROR_NOT_INTITIALIZED, 107	FC2_MODE_22, 110

FC2_MODE_23, 110	FC2_TEMPERATURE, 112
FC2_MODE_24, 110	FC2_TIFF, 109
FC2_MODE_25, 110	FC2_TILT, 112
FC2_MODE_26, 110	FC2_TIMEOUT_INFINITE, 109
FC2_MODE_27, 110	FC2_TIMEOUT_NONE, 109
FC2_MODE_28, 110	FC2_TIMEOUT_UNSPECIFIED, 109
FC2_MODE_29, 110	FC2_TRIGGER_DELAY, 112
FC2_MODE_3, 110	FC2_TRIGGER_MODE, 112
FC2_MODE_30, 110	FC2_UNSPECIFIED_GRAB_MODE, 109
FC2_MODE_31, 110	FC2_UNSPECIFIED_PIXEL_FORMAT, 111
FC2_MODE_4, 110	FC2_UNSPECIFIED_PROPERTY_TYPE, 112
FC2_MODE_5, 110	FC2_VIDEOMODE_1024x768RGB, 112
FC2_MODE_6, 110	FC2_VIDEOMODE_1024x768Y16, 113
FC2_MODE_7, 110	FC2_VIDEOMODE_1024x768Y8, 113
FC2_MODE_8, 110	FC2_VIDEOMODE_1024x768YUV422, 112
FC2 MODE 9, 110	FC2 VIDEOMODE 1280x960RGB, 113
FC2 MODE FORCE 32BITS, 110	FC2_VIDEOMODE_1280x960Y16, 113
FC2_NEAREST_NEIGHBOR_FAST, 106	FC2_VIDEOMODE_1280x960Y8, 113
FC2_NO_COLOR_PROCESSING, 106	FC2_VIDEOMODE_1280x960YUV422, 113
FC2_NUM_FRAMERATES, 108	FC2 VIDEOMODE 1600x1200RGB, 113
FC2 NUM MODES, 110	FC2 VIDEOMODE 1600x1200Y16, 113
	-
FC2_NUM_PIXEL_FORMATS, 111	FC2_VIDEOMODE_1600x1200Y8, 113
FC2_NUM_VIDEOMODES, 113	FC2_VIDEOMODE_1600x1200YUV422, 113
FC2_PAN, 112	FC2_VIDEOMODE_160x120YUV444, 112
FC2_PCIE_BUSSPEED_2_5, 111	FC2_VIDEOMODE_320x240YUV422, 112
FC2_PCIE_BUSSPEED_5_0, 111	FC2_VIDEOMODE_640x480RGB, 112
FC2_PCIE_BUSSPEED_FORCE_32BITS, 111	FC2_VIDEOMODE_640x480Y16, 112
FC2_PCIE_BUSSPEED_UNKNOWN, 111	FC2_VIDEOMODE_640x480Y8, 112
FC2_PGM, 109	FC2_VIDEOMODE_640x480YUV411, 112
FC2_PIXEL_FORMAT_411YUV8, 111	FC2_VIDEOMODE_640x480YUV422, 112
FC2_PIXEL_FORMAT_422YUV8, 111	FC2_VIDEOMODE_800x600RGB, 112
FC2_PIXEL_FORMAT_422YUV8_JPEG, 111	FC2_VIDEOMODE_800x600Y16, 112
FC2_PIXEL_FORMAT_444YUV8, 111	FC2_VIDEOMODE_800x600Y8, 112
FC2_PIXEL_FORMAT_BGR16, 111	FC2_VIDEOMODE_800x600YUV422, 112
FC2_PIXEL_FORMAT_BGRU16, 111	FC2_VIDEOMODE_FORCE_32BITS, 113
FC2_PIXEL_FORMAT_BGRU, 111	FC2_VIDEOMODE_FORMAT7, 113
FC2 PIXEL FORMAT BGR, 111	FC2 WHITE BALANCE, 112
FC2_PIXEL_FORMAT_MONO12, 111	FC2_ZOOM, 112
FC2_PIXEL_FORMAT_MONO16, 111	fc2BandwidthAllocation, 105
FC2_PIXEL_FORMAT_MONO8, 111	fc2BayerTileFormat, 105
FC2 PIXEL FORMAT RAW12, 111	fc2BusCallbackType, 105
FC2 PIXEL FORMAT RAW16, 111	fc2BusSpeed, 106
	fc2ColorProcessingAlgorithm, 106
FC2_PIXEL_FORMAT_RAW8, 111	
FC2_PIXEL_FORMAT_RGB16, 111	fc2DriverType, 106
FC2_PIXEL_FORMAT_RGB8, 111	fc2Error, 107
FC2_PIXEL_FORMAT_RGBU, 111	fc2FrameRate, 108
FC2_PIXEL_FORMAT_RGB, 111	fc2GrabMode, 108
FC2_PIXEL_FORMAT_S_MONO16, 111	fc2GrabTimeout, 109
FC2_PIXEL_FORMAT_S_RGB16, 111	fc2ImageFileFormat, 109
FC2_PNG, 109	fc2InterfaceType, 109
FC2_PPM, 109	fc2Mode, 110
FC2_PROPERTY_TYPE_FORCE_32BITS, 112	fc2PCleBusSpeed, 110
FC2_RAW, 109	fc2PixelFormat, 111
FC2_REMOVAL, 106	fc2PropertyType, 111
FC2_RIGOROUS, 106	fc2VideoMode, 112
FC2_SATURATION, 112	EventCallbackFcn
FC2 SHARPNESS, 112	fc2EventOptions, 138
FC2_SHUTTER, 112	EventData
_ ,	

fc2EventCallbackData, 136	Enumerations, 106
EventDataSize	FC2_BUSSPEED_100BASE_T
fc2EventCallbackData, 136	Enumerations, 106
EventID	FC2_BUSSPEED_10BASE_T
fc2EventCallbackData, 136	Enumerations, 106
EventName	FC2_BUSSPEED_ANY
fc2EventCallbackData, 137	Enumerations, 106
fc2EventOptions, 138	FC2 BUSSPEED FORCE 32BITS
EventTimestamp	Enumerations, 106
fc2EventCallbackData, 137	FC2_BUSSPEED_S100
EventUserData	Enumerations, 106
fc2EventCallbackData, 137	FC2 BUSSPEED S1600
fc2EventOptions, 138	Enumerations, 106
EventUserDataSize	FC2_BUSSPEED_S200
fc2EventCallbackData, 137	Enumerations, 106
fc2EventOptions, 138	FC2 BUSSPEED S3200
exposure	
fc2EmbeddedImageInfo, 135	Enumerations, 106
102Embeddedinagemie, 100	FC2_BUSSPEED_S400
FALSE	Enumerations, 106
MultiSyncLibraryDefs_C.h, 198	FC2_BUSSPEED_S480
TypeDefs, 98	Enumerations, 106
FC2 ARRIVAL	FC2_BUSSPEED_S5000
Enumerations, 106	Enumerations, 106
FC2_AUTO_EXPOSURE	FC2_BUSSPEED_S800
Enumerations, 112	Enumerations, 106
FC2_BANDWIDTH_ALLOCATION_FORCE_32BITS	FC2_BUSSPEED_S_FASTEST
Enumerations, 105	Enumerations, 106
FC2_BANDWIDTH_ALLOCATION_OFF	FC2_BUSSPEED_SPEED_UNKNOWN
Enumerations, 105	Enumerations, 106
FC2_BANDWIDTH_ALLOCATION_ON	FC2_BYTE_ORDER_BIG_ENDIAN
	FlyCapture2Defs_C.h, 188
Enumerations, 105	FC2_BYTE_ORDER_FORCE_32BITS
FC2_BANDWIDTH_ALLOCATION_UNSPECIFIED	FlyCapture2Defs_C.h, 188
Enumerations, 105	FC2_BYTE_ORDER_LITTLE_ENDIAN
FC2_BANDWIDTH_ALLOCATION_UNSUPPORTED	FlyCapture2Defs_C.h, 188
Enumerations, 105	FC2_CALLBACK_TYPE_FORCE_32BITS
FC2_BMP	Enumerations, 106
Enumerations, 109	FC2_COLOR_PROCESSING_ALGORITHM_FORC
FC2_BRIGHTNESS	E 32BITS
Enumerations, 112	_
FC2_BT_BGGR	Enumerations, 106
Enumerations, 105	FC2_DEFAULT
FC2_BT_FORCE_32BITS	Enumerations, 106
Enumerations, 105	FC2_DIRECTIONAL
FC2_BT_GBRG	Enumerations, 106
Enumerations, 105	FC2_DRIVER_1394_CAM
FC2_BT_GRBG	Enumerations, 107
Enumerations, 105	FC2_DRIVER_1394_JUJU
FC2_BT_NONE	Enumerations, 107
Enumerations, 105	FC2_DRIVER_1394_PRO
FC2_BT_RGGB	Enumerations, 107
Enumerations, 105	FC2_DRIVER_1394_RAW1394
FC2 BUFFER FRAMES	Enumerations, 107
Enumerations, 109	FC2_DRIVER_1394_VIDEO1394
FC2_BUS_RESET	Enumerations, 107
Enumerations, 106	FC2_DRIVER_FORCE_32BITS
FC2_BUSSPEED_10000BASE_T	Enumerations, 107
Enumerations, 106	—·····································
	FC2 DRIVER GIGF FILTER
FC2_BUSSPEED_1000BASE_T	FC2_DRIVER_GIGE_FILTER Enumerations, 107

FC2_DRIVER_GIGE_LWF	FC2_ERROR_ISOCH_FAILED
Enumerations, 107	Enumerations, 108
FC2_DRIVER_GIGE_NONE	FC2_ERROR_ISOCH_NOT_STARTED
Enumerations, 107	Enumerations, 108
FC2_DRIVER_GIGE_PRO	FC2_ERROR_ISOCH_RETRIEVE_BUFFER_FAILED
Enumerations, 107	Enumerations, 108
FC2_DRIVER_UNKNOWN	FC2_ERROR_ISOCH_START_FAILED
Enumerations, 107	Enumerations, 108
FC2_DRIVER_USB3_PRO	FC2_ERROR_ISOCH_STOP_FAILED
Enumerations, 107	Enumerations, 108
FC2_DRIVER_USB_CAM	FC2_ERROR_ISOCH_SYNC_FAILED
Enumerations, 107	Enumerations, 108
FC2_DRIVER_USB_NONE	FC2_ERROR_LOW_LEVEL_FAILURE
Enumerations, 107	Enumerations, 107
FC2_DROP_FRAMES	FC2_ERROR_LUT_FAILED
Enumerations, 109	Enumerations, 108
FC2_EDGE_SENSING	FC2_ERROR_MEMORY_ALLOCATION_FAILED
Enumerations, 106	Enumerations, 107
FC2_ERROR_BUFFER_TOO_SMALL	FC2_ERROR_NOT_CONNECTED
Enumerations, 108	Enumerations, 107
FC2_ERROR_BUS_MASTER_FAILED	FC2_ERROR_NOT_FOUND
Enumerations, 108	Enumerations, 107
FC2_ERROR_FAILED_BUS_MASTER_CONNECTION	FC2_ERROR_NOT_IMPLEMENTED
Enumerations, 107	Enumerations, 107
FC2_ERROR_FAILED_GUID	FC2_ERROR_NOT_IN_FORMAT7
Enumerations, 107	Enumerations, 107
FC2_ERROR_FAILED	FC2_ERROR_NOT_INTITIALIZED
Enumerations, 107	Enumerations, 107
FC2_ERROR_FORCE_32BITS	FC2_ERROR_NOT_SUPPORTED
Enumerations, 108	Enumerations, 107
FC2_ERROR_IIDC_FAILED	FC2_ERROR_OK
Enumerations, 108	Enumerations, 107
FC2_ERROR_IMAGE_CONSISTENCY_ERROR	FC2_ERROR_PROPERTY_FAILED
Enumerations, 108	Enumerations, 108
FC2_ERROR_IMAGE_CONVERSION_FAILED	FC2_ERROR_PROPERTY_NOT_PRESENT
Enumerations, 108	Enumerations, 108
FC2_ERROR_IMAGE_LIBRARY_FAILURE	FC2_ERROR_READ_REGISTER_FAILED
Enumerations, 108	Enumerations, 108
FC2 ERROR INCOMPATIBLE DRIVER	FC2_ERROR_REGISTER_FAILED
Enumerations, 108	Enumerations, 108
FC2_ERROR_INIT_FAILED	FC2_ERROR_STROBE_FAILED
Enumerations, 107	Enumerations, 108
FC2_ERROR_INVALID_BUS_MANAGER	FC2_ERROR_TIMEOUT
Enumerations, 107	Enumerations, 107
FC2 ERROR INVALID GENERATION	FC2 ERROR TRIGGER FAILED
Enumerations, 108	Enumerations, 108
FC2_ERROR_INVALID_MODE	FC2_ERROR_UNDEFINED
Enumerations, 107	Enumerations, 107
FC2_ERROR_INVALID_PACKET_SIZE	FC2_ERROR_WRITE_REGISTER_FAILED
Enumerations, 107	Enumerations, 108
FC2_ERROR_INVALID_PARAMETER	FC2_FOCUS
Enumerations, 107	Enumerations, 112
FC2_ERROR_INVALID_SETTINGS	FC2_FRAME_RATE
Enumerations, 107	Enumerations, 112
FC2_ERROR_ISOCH_ALREADY_STARTED	FC2_FRAMERATE_120
Enumerations, 108	Enumerations, 108
FC2_ERROR_ISOCH_BANDWIDTH_EXCEEDED	FC2_FRAMERATE_15
Enumerations, 108	Enumerations, 108

FC2_FRAMERATE_1_875	FC2_LINUX_X86
Enumerations, 108	FlyCapture2Defs_C.h, 188
FC2_FRAMERATE_240	FC2_MAC
Enumerations, 108	FlyCapture2Defs_C.h, 188
FC2_FRAMERATE_30	FC2_MODE_0
Enumerations, 108 FC2_FRAMERATE_3_75	Enumerations, 110 FC2_MODE_1
Enumerations, 108	Enumerations, 110
FC2 FRAMERATE 60	FC2_MODE_10
Enumerations, 108	Enumerations, 110
FC2 FRAMERATE 7 5	FC2 MODE 11
Enumerations, 108	Enumerations, 110
FC2_FRAMERATE_FORCE_32BITS	FC2_MODE_12
Enumerations, 108	Enumerations, 110
FC2_FRAMERATE_FORMAT7	FC2_MODE_13
Enumerations, 108	Enumerations, 110
FC2_FROM_FILE_EXT	FC2_MODE_14
Enumerations, 109	Enumerations, 110
FC2_GAIN	FC2_MODE_15
Enumerations, 112	Enumerations, 110
FC2_GAMMA	FC2_MODE_16
Enumerations, 112	Enumerations, 110
FC2_GRAB_MODE_FORCE_32BITS	FC2_MODE_17
Enumerations, 109 FC2_GRAB_TIMEOUT_FORCE_32BITS	Enumerations, 110 FC2_MODE_18
Enumerations, 109	Enumerations, 110
FC2 HEARTBEAT TIMEOUT	FC2_MODE_19
GigE specific enumerations, 114	Enumerations, 110
FC2_HEARTBEAT	FC2_MODE_2
GigE specific enumerations, 114	Enumerations, 110
FC2_HQ_LINEAR	FC2_MODE_20
Enumerations, 106	Enumerations, 110
FC2_HUE	FC2_MODE_21
roz_noc	TOZ_WODE_ZT
Enumerations, 112	Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS	
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109	Enumerations, 110 FC2_MODE_22 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_IPP	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_29 Enumerations, 110 FC2_MODE_29 Enumerations, 110 FC2_MODE_3
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_IPP Enumerations, 106 FC2_IRIS Enumerations, 112	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_29 Enumerations, 110 FC2_MODE_3 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_IPP Enumerations, 106 FC2_IRIS Enumerations, 112 FC2_JPEG2000	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_29 Enumerations, 110 FC2_MODE_3 Enumerations, 110 FC2_MODE_3 Enumerations, 110 FC2_MODE_3 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_IPP Enumerations, 106 FC2_IRIS Enumerations, 112 FC2_JPEG2000 Enumerations, 109	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_29 Enumerations, 110 FC2_MODE_30 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_IPP Enumerations, 106 FC2_IRIS Enumerations, 112 FC2_JPEG2000 Enumerations, 109 FC2_JPEG	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_29 Enumerations, 110 FC2_MODE_3 Enumerations, 110 FC2_MODE_3 Enumerations, 110 FC2_MODE_30 Enumerations, 110 FC2_MODE_31
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_IPP Enumerations, 106 FC2_IRIS Enumerations, 109 FC2_JPEG2000 Enumerations, 109 FC2_JPEG Enumerations, 109	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_29 Enumerations, 110 FC2_MODE_3 Enumerations, 110 FC2_MODE_30 Enumerations, 110 FC2_MODE_31 Enumerations, 110
Enumerations, 112 FC2_IMAGE_FILE_FORMAT_FORCE_32BITS Enumerations, 109 FC2_INTERFACE_GIGE Enumerations, 110 FC2_INTERFACE_IEEE1394 Enumerations, 110 FC2_INTERFACE_TYPE_FORCE_32BITS Enumerations, 110 FC2_INTERFACE_UNKNOWN Enumerations, 110 FC2_INTERFACE_USB_2 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_INTERFACE_USB_3 Enumerations, 110 FC2_IPP Enumerations, 106 FC2_IRIS Enumerations, 112 FC2_JPEG2000 Enumerations, 109 FC2_JPEG	Enumerations, 110 FC2_MODE_22 Enumerations, 110 FC2_MODE_23 Enumerations, 110 FC2_MODE_24 Enumerations, 110 FC2_MODE_25 Enumerations, 110 FC2_MODE_26 Enumerations, 110 FC2_MODE_27 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_28 Enumerations, 110 FC2_MODE_29 Enumerations, 110 FC2_MODE_3 Enumerations, 110 FC2_MODE_3 Enumerations, 110 FC2_MODE_30 Enumerations, 110 FC2_MODE_31

FC2_MODE_5	FC2_PIXEL_FORMAT_MONO8
Enumerations, 110	Enumerations, 111
FC2_MODE_6	FC2_PIXEL_FORMAT_RAW12
Enumerations, 110	Enumerations, 111
FC2_MODE_7	FC2_PIXEL_FORMAT_RAW16
Enumerations, 110	Enumerations, 111
FC2_MODE_8	FC2_PIXEL_FORMAT_RAW8
Enumerations, 110	Enumerations, 111
FC2_MODE_9	FC2 PIXEL FORMAT RGB16
Enumerations, 110	Enumerations, 111
FC2 MODE FORCE 32BITS	FC2 PIXEL FORMAT RGB8
Enumerations, 110	Enumerations, 111
FC2_NEAREST_NEIGHBOR_FAST	FC2_PIXEL_FORMAT_RGBU
Enumerations, 106	Enumerations, 111
FC2_NO_COLOR_PROCESSING	FC2 PIXEL FORMAT RGB
Enumerations, 106	Enumerations, 111
FC2_NUM_FRAMERATES	FC2_PIXEL_FORMAT_S_MONO16
Enumerations, 108	Enumerations, 111
FC2_NUM_MODES	FC2 PIXEL FORMAT S RGB16
Enumerations, 110	Enumerations, 111
FC2_NUM_PIXEL_FORMATS	FC2_PNG
Enumerations, 111	Enumerations, 109
FC2_NUM_VIDEOMODES	FC2_PPM
Enumerations, 113	Enumerations, 109
FC2_OSTYPE_FORCE_32BITS	FC2_PROPERTY_TYPE_FORCE_32BITS
FlyCapture2Defs_C.h, 188	Enumerations, 112
FC2_PAN	FC2_RAW
Enumerations, 112	Enumerations, 109
FC2_PCIE_BUSSPEED_2_5	FC2_REMOVAL
Enumerations, 111	Enumerations, 106
FC2_PCIE_BUSSPEED_5_0	FC2_RIGOROUS
Enumerations, 111	Enumerations, 106
FC2_PCIE_BUSSPEED_FORCE_32BITS	FC2_SATURATION
Enumerations, 111	Enumerations, 112
FC2_PCIE_BUSSPEED_UNKNOWN	FC2_SHARPNESS
Enumerations, 111	Enumerations, 112
FC2 PGM	FC2_SHUTTER
Enumerations, 109	Enumerations, 112
FC2 PIXEL FORMAT 411YUV8	FC2 STATISTICS BLUE
Enumerations, 111	FlyCapture2Defs_C.h, 189
FC2 PIXEL FORMAT 422YUV8	FC2 STATISTICS FORCE 32BITS
Enumerations, 111	FlyCapture2Defs_C.h, 189
FC2_PIXEL_FORMAT_422YUV8_JPEG	FC2_STATISTICS_GREEN
Enumerations, 111	FlyCapture2Defs_C.h, 189
FC2 PIXEL FORMAT 444YUV8	FC2 STATISTICS GREY
Enumerations, 111	FlyCapture2Defs_C.h, 189
FC2 PIXEL FORMAT BGR16	FC2_STATISTICS_HUE
Enumerations, 111	FlyCapture2Defs_C.h, 189
FC2_PIXEL_FORMAT_BGRU16	FC2_STATISTICS_LIGHTNESS
Enumerations, 111	FlyCapture2Defs_C.h, 189
FC2_PIXEL_FORMAT_BGRU	FC2_STATISTICS_RED
Enumerations, 111	FlyCapture2Defs_C.h, 189
FC2_PIXEL_FORMAT_BGR	FC2_STATISTICS_SATURATION
Enumerations, 111	FlyCapture2Defs_C.h, 189
FC2_PIXEL_FORMAT_MONO12	FC2_TEMPERATURE
Enumerations, 111	Enumerations, 112
FC2_PIXEL_FORMAT_MONO16	FC2_TIFF_ADOBE_DEFLATE
Enumerations, 111	Image saving structures., 120

FC2_TIFF_CCITTFAX3	FC2_VIDEOMODE_1600x1200YUV422
Image saving structures., 120	Enumerations, 113
FC2_TIFF_CCITTFAX4	FC2_VIDEOMODE_160x120YUV444
Image saving structures., 120	Enumerations, 112
FC2 TIFF DEFLATE	FC2 VIDEOMODE 320x240YUV422
Image saving structures., 120	Enumerations, 112
FC2_TIFF_JPEG	FC2_VIDEOMODE_640x480RGB
	Enumerations, 112
Image saving structures., 120	
FC2_TIFF_LZW	FC2_VIDEOMODE_640x480Y16
Image saving structures., 120	Enumerations, 112
FC2_TIFF_NONE	FC2_VIDEOMODE_640x480Y8
Image saving structures., 120	Enumerations, 112
FC2_TIFF_PACKBITS	FC2_VIDEOMODE_640x480YUV411
Image saving structures., 120	Enumerations, 112
FC2_TIFF	FC2_VIDEOMODE_640x480YUV422
Enumerations, 109	Enumerations, 112
FC2_TILT	FC2_VIDEOMODE_800x600RGB
Enumerations, 112	Enumerations, 112
FC2_TIMEOUT_INFINITE	FC2_VIDEOMODE_800x600Y16
Enumerations, 109	Enumerations, 112
FC2 TIMEOUT NONE	FC2_VIDEOMODE_800x600Y8
_	
Enumerations, 109	Enumerations, 112
FC2_TIMEOUT_UNSPECIFIED	FC2_VIDEOMODE_800x600YUV422
Enumerations, 109	Enumerations, 112
FC2_TRIGGER_DELAY	FC2_VIDEOMODE_FORCE_32BITS
Enumerations, 112	Enumerations, 113
FC2_TRIGGER_MODE	FC2_VIDEOMODE_FORMAT7
Enumerations, 112	Enumerations, 113
FC2_UNKNOWN_OS	FC2_WHITE_BALANCE
FlyCapture2Defs_C.h, 188	Enumerations, 112
FC2_UNSPECIFIED_GRAB_MODE	FC2 WINDOWS X64
Enumerations, 109	FlyCapture2Defs_C.h, 188
FC2 UNSPECIFIED PIXEL FORMAT	FC2_WINDOWS_X86
Enumerations, 111	FlyCapture2Defs C.h, 188
FC2_UNSPECIFIED_PROPERTY_TYPE	FC2 ZOOM
Enumerations, 112	Enumerations, 112
FC2_VIDEOMODE_1024x768RGB	FLYCAPTURE2 C API
	
Enumerations, 112	FlyCapture2Platform_C.h, 193
FC2_VIDEOMODE_1024x768Y16	FLYCAPTURE2_C_CALL_CONVEN
Enumerations, 113	FlyCapture2Platform_C.h, 193
FC2_VIDEOMODE_1024x768Y8	FULL_32BIT_VALUE
Enumerations, 113	MultiSyncLibraryDefs_C.h, 198
FC2_VIDEOMODE_1024x768YUV422	TypeDefs, 98
Enumerations, 112	fc2AVIAppend
FC2_VIDEOMODE_1280x960RGB	AVI Recording Operation, 84
Enumerations, 113	fc2AVIClose
FC2_VIDEOMODE_1280x960Y16	AVI Recording Operation, 84
Enumerations, 113	fc2AVIContext
FC2_VIDEOMODE_1280x960Y8	TypeDefs, 98
Enumerations, 113	fc2AVIOpen
FC2_VIDEOMODE_1280x960YUV422	AVI Recording Operation, 85
Enumerations, 113	fc2AVIOption, 121
FC2_VIDEOMODE_1600x1200RGB	frameRate, 121
Enumerations, 113	reserved, 121
FC2_VIDEOMODE_1600x1200Y16	fc2AsyncCommandCallback
Enumerations, 113	Image saving structures., 120
FC2_VIDEOMODE_1600x1200Y8	fc2BMPOption, 122
Enumerations, 113	indexedColor_8bit, 122

received 100	imagoVmitEcilod 129
reserved, 122 fc2BandwidthAllocation	imageXmitFailed, 128
	numCurrents, 128
Enumerations, 105	numResendPacketsReceived, 128
fc2BayerTileFormat	numResendPacketsRequested, 129
Enumerations, 105	numVoltages, 129
fc2BusCallbackType	portErrors, 129
Enumerations, 105	regReadFailed, 129
fc2BusEventCallback	regWriteFailed, 129
Image saving structures., 120	reserved, 129
fc2BusSpeed	temperature, 129
Enumerations, 106	timeSinceBusReset, 129
fc2ByteOrder	timeSinceInitialization, 129
FlyCapture2Defs_C.h, 188	timeStamp, 129
fc2CalculateImageStatistics	fc2CheckDriver
Image Operation, 71	Utilities, 93
fc2CallbackHandle	fc2ColorProcessingAlgorithm
Image saving structures., 120	Enumerations, 106
fc2CameraEventCallback	fc2Config, 129
Image saving structures., 120	asyncBusSpeed, 130
fc2CameraInfo, 122	bandwidthAllocation, 130
applicationIPAddress, 124	grabMode, 130
applicationPort, 124	grabTimeout, 130
bayerTileFormat, 124	highPerformanceRetrieveBuffer, 131
busNumber, 124	isochBusSpeed, 131
ccpStatus, 124	minNumImageNotifications, 131
configROM, 124	numBuffers, 131
defaultGateway, 125	numImageNotifications, 131
driverName, 125	registerTimeout, 131
driverType, 125	registerTimeoutRetries, 132
firmwareBuildTime, 125	reserved, 132
firmwareVersion, 125	fc2ConfigROM, 132
gigEMajorVersion, 125	chipldHi, 133
gigEMinorVersion, 125	chipldLo, 133
iidcVer, 125	nodeVendorld, 133
interfaceType, 125	pszKeyword, 133
ipAddress, 125	reserved, 133
isColorCamera, 126	unitSWVer, 133
macAddress, 126	unitSpecId, 133
maximumBusSpeed, 126	unitSubSWVer, 133
modelName, 126	vendorUniqueInfo_0, 133
nodeNumber, 126	vendorUniqueInfo_1, 133
pcieBusSpeed, 126	vendorUniqueInfo 2, 134
reserved, 126	vendorUniqueInfo 3, 134
sensorInfo, 126	fc2Connect
sensorResolution, 126	Connection and Image Retrieval, 19
serialNumber, 126	fc2Context
subnetMask, 127	TypeDefs, 98
userDefinedName, 127	fc2ConvertImage
vendorName, 127	Image Operation, 71
xmlURL1, 127	fc2ConvertImageTo
xmlURL2, 127	Image Operation, 71
fc2CameraStats, 127	fc2CreateAVI
cameraCurrents, 128	AVI Recording Operation, 85
cameraPowerUp, 128	fc2CreateGUIContext
cameraVoltages, 128	FlyCapture2GUI_C.h, 190
imageCorrupt, 128	fc2CreateImage
imageDriverDropped, 128	Image Operation, 72
imageDropped, 128	fc2CreateImageStatistics
	-

Image Statistics Operation, 78	fc2FireBusReset
fc2CreateTopologyNode	Bus Manager Operation, 11
TopologyNode Operation, 88	fc2FireSoftwareTrigger
fc2DestroyAVI	Trigger, 31
AVI Recording Operation, 85	fc2FireSoftwareTriggerBroadcast
fc2DestroyGUIContext	Trigger, 32
FlyCapture2GUI_C.h, 190	fc2ForceAllIPAddressesAutomatically
fc2DestroyImage	Bus Manager Operation, 11
Image Operation, 72	fc2ForceIPAddressAutomatically
fc2DestroyImageStatistics	Bus Manager Operation, 11
Image Statistics Operation, 78	fc2ForceIPAddressToCamera
fc2DestroyTopologyNode	Bus Manager Operation, 11
TopologyNode Operation, 88	fc2Format7ImageSettings, 138
fc2DetermineBitsPerPixel	height, 139
Image Operation, 72	mode, 139
fc2Disconnect	offsetX, 139
	offsetY, 139
Connection and Image Retrieval, 20	
fc2DiscoverGigECameras	pixelFormat, 139
Bus Manager Operation, 10	reserved, 139
fc2DiscoverGigEPacketSize	width, 139
GigE property manipulation, 60	fc2Format7Info, 139
fc2Disonnect	imageHStepSize, 140
FlyCapture2GUI_C.h, 190	imageVStepSize, 140
fc2DriverType	maxHeight, 140
Enumerations, 106	maxPacketSize, 141
fc2EmbeddedImageInfo, 134	maxWidth, 141
brightness, 135	minPacketSize, 141
exposure, 135	mode, 141
frameCounter, 135	offsetHStepSize, 141
GPIOPinState, 135	offsetVStepSize, 141
gain, 135	packetSize, 141
ROIPosition, 135	percentage, 141
shutter, 135	pixelFormatBitField, 141
strobePattern, 135	reserved, 141
timestamp, 135	vendorPixelFormatBitField, 142
whiteBalance, 135	fc2Format7PacketInfo, 142
fc2EmbeddedImageInfoProperty, 135	maxBytesPerPacket, 142
available, 136	recommendedBytesPerPacket, 142
onOff, 136	reserved, 142
fc2EnableLUT	unitBytesPerPacket, 143
Look Up Table, 40	fc2FrameRate
fc2Error	Enumerations, 108
Enumerations, 107	fc2GUIConnect
fc2ErrorToDescription	FlyCapture2GUI_C.h, 190
Utilities, 94	fc2GUIDisconnect
fc2EventCallbackData, 136	FlyCapture2GUI_C.h, 191
EventData, 136	fc2GetActiveLUTBank
EventDataSize, 136	Look Up Table, 41
EventID, 136	fc2GetCameraFromIPAddress
EventName, 137	Bus Manager Operation, 12
EventTimestamp, 137	fc2GetCameraFromIndex
EventUserData, 137	Bus Manager Operation, 12
EventUserDataSize, 137	fc2GetCameraFromSerialNumber
fc2EventOptions, 137	Bus Manager Operation, 13
EventCallbackFcn, 138	fc2GetCameraInfo
EventName, 138	Information and Properties, 26
EventUserData, 138	fc2GetCameraSerialNumberFromIndex
EventUserDataSize, 138	Bus Manager Operation, 13

fc2GetChannelHistogram	fc2GetLibraryVersion
Image Statistics Operation, 78	Utilities, 94
fc2GetChannelMean	fc2GetMemoryChannel
Image Statistics Operation, 79	Memory Channels, 45
fc2GetChannelNumPixelValues	fc2GetMemoryChannelInfo
Image Statistics Operation, 79	Memory Channels, 45
fc2GetChannelPixelValueRange	fc2GetNumOfCameras
Image Statistics Operation, 79	Bus Manager Operation, 14
fc2GetChannelRange	fc2GetNumOfDevices
Image Statistics Operation, 80	Bus Manager Operation, 14
fc2GetChannelStatus	fc2GetNumStreamChannels
	GigE image stream configuration, 68
Image Statistics Operation, 80 fc2GetConfiguration	fc2GetProperty
	· ·
Connection and Image Retrieval, 20	Information and Properties, 26
fc2GetDefaultColorProcessing	fc2GetPropertyInfo
Image Operation, 73	Information and Properties, 27
fc2GetDefaultOutputFormat	fc2GetRegisterString
Image Operation, 73	Register Operation, 48
fc2GetDeviceFromIndex	fc2GetStrobe
Bus Manager Operation, 13	Strobe, 37
fc2GetDriverDeviceName	fc2GetStrobeInfo
Utilities, 94	Strobe, 37
fc2GetEmbeddedImageInfo	fc2GetSystemInfo
Memory Channels, 44	Utilities, 94
fc2GetFormat7Configuration	fc2GetTopology
Format7, 53	Bus Manager Operation, 15
fc2GetFormat7Info	fc2GetTriggerDelay
Format7, 53	Trigger, 32
fc2GetGPIOPinDirection	fc2GetTriggerDelayInfo
General Purpose Input / Output, 29	Trigger, 32
fc2GetGigEConfig	fc2GetTriggerMode
GigE image stream configuration, 67	Trigger, 33
fc2GetGigEImageBinningSettings	fc2GetTriggerModeInfo
GigE image binning settings, 65	Trigger, 33
fc2GetGigEImageSettings	fc2GetUsbLinkInfo
GigE image settings, 62	Bus Manager Operation, 15
fc2GetGigEImageSettingsInfo	fc2GetUsbPortStatus
GigE image settings, 62	Bus Manager Operation, 15
fc2GetGigEImagingMode	fc2GetVideoModeAndFrameRate
GigE image settings, 63	DCAM Formats, 51
fc2GetGigEProperty	fc2GetVideoModeAndFrameRateInfo
GigE property manipulation, 60	DCAM Formats, 51
fc2GetGigEStreamChannelInfo	fc2GigEConfig, 143
GigE image stream configuration, 67	enablePacketResend, 143
fc2GetImageData	registerTimeout, 143
Image Operation, 73	registerTimeout, 143
fc2GetImageStatistics	_
•	reserved, 144
Image Statistics Operation, 80	fc2GigEImageSettings, 144
fc2GetImageTimeStamp	height, 144
Image Operation, 74	offsetX, 144
fc2GetInterfaceTypeFromGuid	offsetY, 144
Bus Manager Operation, 14	pixelFormat, 145
fc2GetLUTBankInfo	reserved, 145
Look Up Table, 41	width, 145
fc2GetLUTChannel	fc2GigEImageSettingsInfo, 145
Look Up Table, 41	imageHStepSize, 146
fc2GetLUTInfo	imageVStepSize, 146
Look Up Table, 42	maxHeight, 146

maxWidth, 146	TypeDefs, 99
offsetHStepSize, 146	fc2ImageMetadata, 151
offsetVStepSize, 146	embeddedBrightness, 152
pixelFormatBitField, 146	embeddedExposure, 152
reserved, 146	embeddedFrameCounter, 152
vendorPixelFormatBitField, 146	embeddedGPIOPinState, 152
fc2GigEProperty, 147	embeddedGain, 152
isReadable, 147	embeddedROIPosition, 153
isWritable, 147	embeddedShutter, 153
max, 147	embeddedStrobePattern, 153
min, 148	embeddedTimeStamp, 153
propType, 148	embeddedWhiteBalance, 153
reserved, 148	reserved, 153
value, 148	fc2ImageStatisticsContext
fc2GigEPropertyType	TypeDefs, 99
GigE specific enumerations, 114	fc2ImageStatisticsDisableAll
fc2GigEStreamChannel, 148	Image Statistics Operation, 81
destinationlpAddress, 149	fc2ImageStatisticsEnableAll
•	3
doNotFragment, 149	Image Statistics Operation, 81 fc2ImageStatisticsEnableGreyOnly
hostPort, 149	
interPacketDelay, 149	Image Statistics Operation, 81
networkInterfaceIndex, 149	fc2ImageStatisticsEnableHSLOnly
packetSize, 149	Image Statistics Operation, 82
reserved, 149	fc2ImageStatisticsEnableRGBOnly
sourcePort, 149	Image Statistics Operation, 82
fc2GrabMode	fc2InterfaceType
Enumerations, 108	Enumerations, 109
fc2GrabTimeout	fc2InternalContext, 153
Enumerations, 109	pBusMgr, 154
fc2GuiContext	pCamera, 154
TypeDefs, 99	fc2InternalGuiContext, 154
fc2H264Open	pCameraControlDlg, 154
AVI Recording Operation, 86	pCameraSelectionDlg, 154
fc2H264Option, 150	fc2InternalImageCallback, 154
bitrate, 150	pCallback, 154
frameRate, 150	pCallbackData, 154
height, 150	fc2lsCameraControlable
reserved, 150	Bus Manager Operation, 16
width, 150	fc2lsVisible
fc2Hide	FlyCapture2GUI_C.h, 191
FlyCapture2GUI_C.h, 191	fc2JPEGOption, 155
fc2IPAddress, 155	progressive, 155
octets, 155	quality, 155
fc2lmage, 151	reserved, 156
bayerFormat, 151	fc2JPG2Option, 156
cols, 151	quality, 1 <mark>56</mark>
dataSize, 151	reserved, 156
format, 151	fc2LUTData, 157
imageImpl, 151	enabled, 157
pData, 151	inputBitDepth, 157
receivedDataSize, 151	numBanks, 157
rows, 151	numChannels, 158
stride, 151	numEntries, 158
fc2ImageEventCallback	outputBitDepth, 158
Image saving structures., 120	reserved, 158
fc2ImageFileFormat	supported, 158
Enumerations, 109	fc2LaunchBrowser
fc2ImageImpl	Utilities, 96
<u> </u>	•

fc2LaunchCommand Utilities, 96	fc2RestoreFromMemoryChannel Memory Channels, 45
fc2LaunchCommandAsync	fc2RetrieveBuffer
Utilities, 96	Connection and Image Retrieval, 20
fc2LaunchHelp	fc2SaveImage
Utilities, 97	Image Operation, 74
fc2MACAddress, 158	
	fc2SaveImageWithOption
octets, 159	Image Operation, 74
fc2MJPGOpen	fc2SaveToMemoryChannel
AVI Recording Operation, 86	Memory Channels, 46
fc2MJPGOption, 159	fc2SetActiveLUTBank
frameRate, 159	Look Up Table, 42
quality, 159	fc2SetCallback
reserved, 159	Connection and Image Retrieval, 21
fc2Mode	fc2SetChannelStatus
Enumerations, 110	Image Statistics Operation, 82
fc2NodeType	fc2SetConfiguration
FlyCapture2Defs_C.h, 188	Connection and Image Retrieval, 21
fc2OSType	fc2SetDefaultColorProcessing
FlyCapture2Defs_C.h, 188	Image Operation, 74
fc2PCleBusSpeed	fc2SetDefaultOutputFormat
Enumerations, 110	Image Operation, 75
fc2PGMOption, 160	fc2SetEmbeddedImageInfo
binaryFile, 160	Memory Channels, 46
reserved, 160	fc2SetFormat7Configuration
fc2PGRGuid, 160	Format7, 54
value, 161	fc2SetFormat7ConfigurationPacket
fc2PNGOption, 161	Format7, 54
compressionLevel, 161	fc2SetGPIOPinDirection
interlaced, 161	General Purpose Input / Output, 29
reserved, 161	fc2SetGPIOPinDirectionBroadcast
fc2PPMOption, 162	General Purpose Input / Output, 30
binaryFile, 162	fc2SetGigEConfig
reserved, 162	GigE image stream configuration, 68
fc2PixelFormat	fc2SetGigEImageBinningSettings
Enumerations, 111	GigE image binning settings, 65
fc2PortType	fc2SetGigEImageSettings
FlyCapture2Defs_C.h, 188	GigE image settings, 63
fc2PropertyType	fc2SetGigEImagingMode
Enumerations, 111	GigE image settings, 64
fc2QueryGigEImagingMode	fc2SetGigEProperty
GigE image settings, 63	GigE property manipulation, 61
fc2ReadGVCPMemory	fc2SetGigEStreamChannelInfo
GVCP Register Operation, 56	GigE image stream configuration, 68
fc2ReadGVCPRegister	
	fc2SetImageData
GVCP Register Operation, 57	Image Operation, 75
fc2ReadGVCPRegisterBlock	fc2SetImageDimensions
GVCP Register Operation, 57	Image Operation, 76
fc2ReadPhyRegister	fc2SetLUTChannel
Bus Manager Operation, 16	Look Up Table, 42
fc2ReadRegister	fc2SetProperty
Register Operation, 48	Information and Properties, 27
fc2ReadRegisterBlock	fc2SetPropertyBroadcast
Register Operation, 49	Information and Properties, 28
fc2RegisterCallback	fc2SetStrobe
Bus Manager Operation, 16	Strobe, 38
fc2RescanBus	fc2SetStrobeBroadcast
Bus Manager Operation, 17	Strobe, 38

4 ao -= 1	
fc2SetTriggerDelay	Image saving structures., 120
Trigger, 34	fc2TIFFOption, 167
fc2SetTriggerDelayBroadcast	compression, 167
Trigger, 34	reserved, 167
fc2SetTriggerMode	fc2TimeStamp, 168
Trigger, 35	cycleCount, 168
fc2SetTriggerModeBroadcast	cycleOffset, 168
Trigger, 35	cycleSeconds, 168
fc2SetUserBuffers	microSeconds, 168
Connection and Image Retrieval, 21	reserved, 168
fc2SetVideoModeAndFrameRate	seconds, 168
DCAM Formats, 52	fc2TopologyNodeAddChild
fc2Show	TopologyNode Operation, 88
FlyCapture2GUI_C.h, 191	fc2TopologyNodeAddPortType
fc2ShowModal	TopologyNode Operation, 89
FlyCapture2GUI_C.h, 192	fc2TopologyNodeAssignGuidToNode
fc2StartCapture	TopologyNode Operation, 89
Connection and Image Retrieval, 22	fc2TopologyNodeAssignGuidToNodeEx
fc2StartCaptureCallback	TopologyNode Operation, 89
Connection and Image Retrieval, 22	fc2TopologyNodeContext
fc2StartSyncCapture	TypeDefs, 99
Connection and Image Retrieval, 23	fc2TopologyNodeGetChild
fc2StartSyncCaptureCallback	TopologyNode Operation, 90
Connection and Image Retrieval, 23	fc2TopologyNodeGetDeviceId
fc2StatisticsChannel	TopologyNode Operation, 90
FlyCapture2Defs_C.h, 189	fc2TopologyNodeGetGuid
fc2StopCapture	TopologyNode Operation, 90
Connection and Image Retrieval, 24	fc2TopologyNodeGetInterfaceType
fc2StrobeControl, 162	TopologyNode Operation, 90
delay, 163	fc2TopologyNodeGetNodeType
duration, 163	TopologyNode Operation, 91
onOff, 163	fc2TopologyNodeGetNumChildren
polarity, 163	TopologyNode Operation, 91
reserved, 163	fc2TopologyNodeGetNumPorts
source, 163	TopologyNode Operation, 91
fc2StrobeInfo, 163	fc2TopologyNodeGetPortType
maxValue, 164	TopologyNode Operation, 92
minValue, 164	fc2TriggerDelay, 169
onOffSupported, 164	absControl, 170
polaritySupported, 164	absValue, 170
present, 164	autoManualMode, 170
readOutSupported, 164	onOff, 170
reserved, 165	onePush, 170
source, 165	present, 170
fc2SystemInfo, 165	reserved, 170
byteOrder, 166	type, 170
cpuDescription, 166	valueA, 170
driverList, 166	valueB, 170
gpuDescription, 166	fc2TriggerDelayInfo, 171
libraryList, 166	absMax, 172
numCpuCores, 166	absMin, 172
osDescription, 166	absValSupported, 172
osType, 166	autoSupported, 172
reserved, 166	manualSupported, 172
screenHeight, 166	max, 172
screenWidth, 167	min, 172
sysMemSize, 167	onOffSupported, 172
fc2TIFFCompressionMethod	onePushSupported, 172

pUnitAbbr, 173	BUS, 188
pUnits, 173	CAMERA, 188
present, 173	COMPUTER, 188
readOutSupported, 173	CONNECTED_TO_CHILD, 189
reserved, 173	CONNECTED_TO_PARENT, 189
type, 173	FC2_BYTE_ORDER_BIG_ENDIAN, 188
fc2TriggerMode, 173	FC2_BYTE_ORDER_FORCE_32BITS, 188
mode, 174	FC2_BYTE_ORDER_LITTLE_ENDIAN, 188
onOff, 174	FC2 LINUX X64, 188
parameter, 174	FC2 LINUX X86, 188
polarity, 174	FC2_MAC, 188
reserved, 174	FC2_OSTYPE_FORCE_32BITS, 188
source, 174	FC2_STATISTICS_BLUE, 189
fc2TriggerModeInfo, 175	FC2 STATISTICS FORCE 32BITS, 189
modeMask, 175	FC2 STATISTICS GREEN, 189
onOffSupported, 175	FC2_STATISTICS_GREY, 189
polaritySupported, 176	FC2 STATISTICS HUE, 189
present, 176	FC2 STATISTICS LIGHTNESS, 189
readOutSupported, 176	FC2 STATISTICS RED, 189
reserved, 176	FC2_STATISTICS_SATURATION, 189
softwareTriggerSupported, 176	FC2 UNKNOWN OS, 188
	_ :
sourceMask, 176	FC2_WINDOWS_X64, 188 FC2_WINDOWS_X86, 188
valueReadable, 176	
fc2UnregisterCallback	fc2ByteOrder, 188
Bus Manager Operation, 17	fc2NodeType, 188
fc2ValidateFormat7Settings	fc2OSType, 188
Format7, 54	fc2PortType, 188
fc2Version, 176	fc2StatisticsChannel, 189
build, 177	NODE, 188
major, 177	NOT_CONNECTED, 189
minor, 177	FlyCapture2GUI_C.h, 189
type, 177	fc2CreateGUIContext, 190
fc2VideoMode	fc2DestroyGUIContext, 190
Enumerations, 112	fc2Disonnect, 190
fc2WaitForBufferEvent	fc2GUIConnect, 190
Connection and Image Retrieval, 24	fc2GUIDisconnect, 191
fc2WriteGVCPMemory	fc2Hide, 191
GVCP Register Operation, 57	fc2lsVisible, 191
fc2WriteGVCPRegister	fc2Show, 191
GVCP Register Operation, 58	fc2ShowModal, 192
fc2WriteGVCPRegisterBlock	FlyCapture2Internal_C.h, 192
GVCP Register Operation, 58	IsContextValid, 193
fc2WriteGVCPRegisterBroadcast	IsGuiContextValid, 193
GVCP Register Operation, 58	SyncCppImageToStruct, 193
fc2WritePhyRegister	FlyCapture2Platform_C.h, 193
Bus Manager Operation, 17	FLYCAPTURE2_C_API, 193
fc2WriteRegister	FLYCAPTURE2_C_CALL_CONVEN, 193
Register Operation, 49	FlyCapture2Private_C.h, 193
fc2WriteRegisterBlock	GetInternal, 193
Register Operation, 50	format
fc2WriteRegisterBroadcast	fc2Image, 151
Register Operation, 50	Format7, 53
firmwareBuildTime	fc2GetFormat7Configuration, 53
fc2CameraInfo, 125	fc2GetFormat7Info, 53
firmwareVersion	fc2SetFormat7Configuration, 54
fc2CameraInfo, 125	fc2SetFormat7ConfigurationPacket, 54
FlyCapture2_C.h, 179	fc2ValidateFormat7Settings, 54
FlyCapture2Defs_C.h, 179	frameCounter
- ' -	

fc2EmbeddedImageInfo, 135	grabTimeout
frameRate	fc2Config, 130
fc2AVIOption, 121	•
fc2H264Option, 150	height
•	-
fc2MJPGOption, 159	fc2Format7ImageSettings, 139
	fc2GigEImageSettings, 144
GPIOPinState	fc2H264Option, 150
fc2EmbeddedImageInfo, 135	highPerformanceRetrieveBuffer
GVCP Register Operation, 56	fc2Config, 131
fc2ReadGVCPMemory, 56	hostPort
fc2ReadGVCPRegister, 57	
g .	fc2GigEStreamChannel, 149
fc2ReadGVCPRegisterBlock, 57	
fc2WriteGVCPMemory, 57	IIDC specific structures, 118
fc2WriteGVCPRegister, 58	iidcVer
fc2WriteGVCPRegisterBlock, 58	fc2CameraInfo, 125
fc2WriteGVCPRegisterBroadcast, 58	Image Operation, 70
	fc2CalculateImageStatistics, 71
gain	
fc2EmbeddedImageInfo, 135	fc2ConvertImage, 71
General Purpose Input / Output, 29	fc2ConvertImageTo, 71
fc2GetGPIOPinDirection, 29	fc2CreateImage, 72
fc2SetGPIOPinDirection, 29	fc2DestroyImage, 72
fc2SetGPIOPinDirectionBroadcast, 30	fc2DetermineBitsPerPixel, 72
GetInternal	fc2GetDefaultColorProcessing, 73
FlyCapture2Private_C.h, 193	fc2GetDefaultOutputFormat, 73
GigE image binning settings, 65	fc2GetImageData, 73
fc2GetGigEImageBinningSettings, 65	fc2GetImageTimeStamp, 74
fc2SetGigEImageBinningSettings, 65	fc2SaveImage, 74
GigE image settings, 62	fc2SaveImageWithOption, 74
fc2GetGigEImageSettings, 62	fc2SetDefaultColorProcessing, 74
fc2GetGigEImageSettingsInfo, 62	fc2SetDefaultOutputFormat, 75
fc2GetGigEImagingMode, 63	fc2SetImageData, 75
fc2QueryGigEImagingMode, 63	fc2SetImageDimensions, 76
fc2SetGigEImageSettings, 63	Image saving structures., 119
fc2SetGigEImagingMode, 64	FC2_TIFF_ADOBE_DEFLATE, 120
	FC2 TIFF CCITTFAX3, 120
GigE image stream configuration, 67	
fc2GetGigEConfig, 67	FC2_TIFF_CCITTFAX4, 120
fc2GetGigEStreamChannelInfo, 67	FC2_TIFF_DEFLATE, 120
fc2GetNumStreamChannels, 68	FC2_TIFF_JPEG, 120
fc2SetGigEConfig, 68	FC2_TIFF_LZW, 120
fc2SetGigEStreamChannelInfo, 68	FC2_TIFF_NONE, 120
_	FC2_TIFF_PACKBITS, 120
GigE property manipulation, 60	
fc2DiscoverGigEPacketSize, 60	fc2AsyncCommandCallback, 120
fc2GetGigEProperty, 60	fc2BusEventCallback, 120
fc2SetGigEProperty, 61	fc2CallbackHandle, 120
GigE specific enumerations, 114	fc2CameraEventCallback, 120
FC2_HEARTBEAT_TIMEOUT, 114	fc2ImageEventCallback, 120
FC2_HEARTBEAT, 114	fc2TIFFCompressionMethod, 120
fc2GigEPropertyType, 114	Image Statistics Operation, 77
PACKET_DELAY, 114	fc2CreateImageStatistics, 78
PACKET_SIZE, 114	fc2DestroyImageStatistics, 78
GigE specific structures, 117	fc2GetChannelHistogram, 78
gigEMajorVersion	fc2GetChannelMean, 79
fc2CameraInfo, 125	fc2GetChannelNumPixelValues, 79
gigEMinorVersion	fc2GetChannelPixelValueRange, 79
fc2CameraInfo, 125	fc2GetChannelRange, 80
gpuDescription	fc2GetChannelStatus, 80
fc2SystemInfo, 166	fc2GetImageStatistics, 80
grabMode	fc2ImageStatisticsDisableAll, 81
-	
fc2Config, 130	fc2ImageStatisticsEnableAll, 81

fc2ImageStatisticsEnableGreyOnly, 81 fc2ImageStatisticsEnableHSLOnly, 82	fc2SetActiveLUTBank, 42 fc2SetLUTChannel, 42
fc2ImageStatisticsEnableRGBOnly, 82	,
fc2SetChannelStatus, 82	MAX_STRING_LENGTH
imageCorrupt	MultiSyncLibraryDefs_C.h, 198
fc2CameraStats, 128	TypeDefs, 98
imageDriverDropped	MULTISYNCLIBRARY_C_API
	MultiSyncLibraryPlatform_C.h, 199
fc2CameraStats, 128	MULTISYNCLIBRARY_C_CALL_CONVEN
imageDropped	MultiSyncLibraryPlatform_C.h, 199
fc2CameraStats, 128	macAddress
imageHStepSize	fc2CameraInfo, 126
fc2Format7Info, 140	
fc2GigEImageSettingsInfo, 146	major
imageImpl	fc2Version, 177
fc2Image, 151	manualSupported
imageVStepSize	fc2TriggerDelayInfo, 172
fc2Format7Info, 140	max
fc2GigEImageSettingsInfo, 146	fc2GigEProperty, 147
imageXmitFailed	fc2TriggerDelayInfo, 172
fc2CameraStats, 128	maxBytesPerPacket
indexedColor_8bit	fc2Format7PacketInfo, 142
fc2BMPOption, 122	maxHeight
Information and Properties, 26	fc2Format7Info, 140
fc2GetCameraInfo, 26	fc2GigEImageSettingsInfo, 146
fc2GetProperty, 26	maxPacketSize
fc2GetPropertyInfo, 27	fc2Format7Info, 141
fc2SetProperty, 27	maxValue
fc2SetPropertyBroadcast, 28	fc2StrobeInfo, 164
· ·	maxWidth
inputBitDepth	fc2Format7Info, 141
fc2LUTData, 157	fc2GigEImageSettingsInfo, 146
interPacketDelay	maximumBusSpeed
fc2GigEStreamChannel, 149	fc2CameraInfo, 126
interfaceType	Memory Channels, 44
fc2CameraInfo, 125	fc2GetEmbeddedImageInfo, 44
interlaced	fc2GetMemoryChannel, 45
fc2PNGOption, 161	
ipAddress	fc2GetMemoryChannelInfo, 45
fc2CameraInfo, 125	fc2RestoreFromMemoryChannel, 45
isColorCamera	fc2SaveToMemoryChannel, 46
fc2CameraInfo, 126	fc2SetEmbeddedImageInfo, 46
IsContextValid	microSeconds
FlyCapture2Internal_C.h, 193	fc2TimeStamp, 168
IsGuiContextValid	min
FlyCapture2Internal_C.h, 193	fc2GigEProperty, 148
isReadable	fc2TriggerDelayInfo, 172
fc2GigEProperty, 147	minNumImageNotifications
isWritable	fc2Config, 131
fc2GigEProperty, 147	minPacketSize
isochBusSpeed	fc2Format7Info, 141
fc2Config, 131	minValue
1020011lig, 101	fc2StrobeInfo, 164
libraryList	minor
fc2SystemInfo, 166	fc2Version, 177
Look Up Table, 40	mode
fc2EnableLUT, 40	fc2Format7ImageSettings, 139
fc2GetActiveLUTBank, 41	fc2Format7Info, 141
fc2GetLUTBankInfo, 41	fc2TriggerMode, 174
fc2GetLUTChannel, 41	modeMask
fc2GetLUTInfo, 42	fc2TriggerModeInfo, 175

modelName	numBuffers
fc2CameraInfo, 126	fc2Config, 131
MultiSyncLibrary_C.h, 193	numChannels
syncCreateContext, 194	fc2LUTData, 158
syncDestroyContext, 194	numCpuCores
syncDisableCrossPCSynchronization, 195	fc2SystemInfo, 166
syncEnableCrossPCSynchronization, 195	numCurrents
syncGetStatus, 195	fc2CameraStats, 128
syncGetTimeSinceSynced, 195	numEntries
synclsTimingBusConnected, 196	fc2LUTData, 158
syncQueryCrossPCSynchronizationSetting, 196	numImageNotifications
syncRescanMasterTimingBus, 196	fc2Config, 131
syncStart, 197	numResendPacketsReceived
syncStop, 197	fc2CameraStats, 128
MultiSyncLibraryDefs_C.h, 197	numResendPacketsRequested
BOOL, 198	fc2CameraStats, 129
FALSE, 198	numVoltages
FULL 32BIT VALUE, 198	fc2CameraStats, 129
MAX_STRING_LENGTH, 198	
SYNC ERROR ALREADY STARTED, 198	octets
SYNC_ERROR_ALREADY_STOPPED, 198	fc2IPAddress, 155
SYNC_ERROR_CONTEXT_NOT_INITIALIZED,	fc2MACAddress, 159
198	offsetHStepSize
SYNC_ERROR_FAILED, 198	fc2Format7Info, 141
SYNC_ERROR_OK, 198	fc2GigEImageSettingsInfo, 146
SYNC_ERROR_UNKNOWN_ERROR, 198	offsetVStepSize
SYNC_MESSAGE_BUS_RESET, 199	fc2Format7Info, 141
SYNC_MESSAGE_DEVICE_ERROR, 199	fc2GigEImageSettingsInfo, 146
SYNC_MESSAGE_FAILED, 199	offsetX
SYNC_MESSAGE_NOMASTER, 199	fc2Format7ImageSettings, 139
SYNC_MESSAGE_NOT_ENOUGH_DEVICES,	fc2GigEImageSettings, 144
199	offsetY
SYNC_MESSAGE_NOT_INITIALIZED, 199	fc2Format7ImageSettings, 139
SYNC_MESSAGE_OK, 199	fc2GigEImageSettings, 144
SYNC_MESSAGE_STARTED, 199	onOff
SYNC_MESSAGE_STOPPED, 199	fc2EmbeddedImageInfoProperty, 136
SYNC_MESSAGE_SYNCING, 199	fc2StrobeControl, 163
SYNC_MESSAGE_THREAD_ERROR, 199	fc2TriggerDelay, 170
SYNC_MESSAGE_UNKNOWN_ERROR, 199	fc2TriggerMode, 174
syncContext, 198	onOffSupported
syncError, 198	fc2StrobeInfo, 164
syncMessage, 198	fc2TriggerDelayInfo, 172
TRUE, 198	fc2TriggerModeInfo, 175
MultiSyncLibraryPlatform_C.h, 199	onePush
MULTISYNCLIBRARY_C_API, 199	fc2TriggerDelay, 170
MULTISYNCLIBRARY_C_CALL_CONVEN, 199	onePushSupported
	fc2TriggerDelayInfo, 172
NODE	osDescription
FlyCapture2Defs_C.h, 188	fc2SystemInfo, 166
NOT_CONNECTED	osType
FlyCapture2Defs_C.h, 189	fc2SystemInfo, 166
networkInterfaceIndex	outputBitDepth
fc2GigEStreamChannel, 149	fc2LUTData, 158
nodeNumber	DAGUET DELAY
fc2CameraInfo, 126	PACKET_DELAY
nodeVendorld	GigE specific enumerations, 114
fc2ConfigROM, 133	PACKET_SIZE
numBanks	GigE specific enumerations, 114
fc2LUTData, 157	pBusMgr

fc2InternalContext, 154	readOutSupported
pCallback	fc2StrobeInfo, 164
fc2InternalImageCallback, 154	fc2TriggerDelayInfo, 173
pCallbackData	fc2TriggerModeInfo, 176
fc2InternalImageCallback, 154	receivedDataSize
pCamera	fc2Image, 151
fc2InternalContext, 154	recommendedBytesPerPacket
pCameraControlDlg	fc2Format7PacketInfo, 142
fc2InternalGuiContext, 154	regReadFailed
pCameraSelectionDlg fc2InternalGuiContext, 154	fc2CameraStats, 129
	regWriteFailed
pData fc2Image, 151	fc2CameraStats, 129
pUnitAbbr	Register Operation, 48
fc2TriggerDelayInfo, 173	fc2GetRegisterString, 48
pUnits	fc2ReadRegister, 48 fc2ReadRegisterBlock, 49
fc2TriggerDelayInfo, 173	fc2WriteRegister, 49
packetSize	fc2WriteRegister, 49
fc2Format7Info, 141	fc2WriteRegisterBroadcast, 50
fc2GigEStreamChannel, 149	registerTimeout
parameter	fc2Config, 131
fc2TriggerMode, 174	fc2GigEConfig, 143
pcieBusSpeed	registerTimeoutRetries
fc2CameraInfo, 126	fc2Config, 132
percentage	fc2GigEConfig, 143
fc2Format7Info, 141	reserved
pixelFormat	fc2AVIOption, 121
fc2Format7ImageSettings, 139	fc2BMPOption, 122
fc2GigEImageSettings, 145	fc2CameraInfo, 126
pixelFormatBitField	fc2CameraStats, 129
fc2Format7Info, 141	fc2Config, 132
fc2GigEImageSettingsInfo, 146	fc2ConfigROM, 133
polarity	fc2Format7ImageSettings, 139
fc2StrobeControl, 163	fc2Format7Info, 141
fc2TriggerMode, 174	fc2Format7PacketInfo, 142
polaritySupported	fc2GigEConfig, 144
fc2StrobeInfo, 164	fc2GigEImageSettings, 145
fc2TriggerModeInfo, 176	fc2GigEImageSettingsInfo, 146
portErrors	fc2GigEProperty, 148
fc2CameraStats, 129	fc2GigEStreamChannel, 149
present	fc2H264Option, 150
fc2StrobeInfo, 164	fc2ImageMetadata, 153
fc2TriggerDelay, 170	fc2JPEGOption, 156
fc2TriggerDelayInfo, 173	fc2JPG2Option, 156
fc2TriggerModeInfo, 176	fc2LUTData, 158
progressive	fc2MJPGOption, 159
fc2JPEGOption, 155	fc2PGMOption, 160
propType	fc2PNGOption, 161
fc2GigEProperty, 148	fc2PPMOption, 162
pszKeyword	fc2StrobeControl, 163
fc2ConfigROM, 133	fc2StrobeInfo, 165
quality	fc2SystemInfo, 166
quality fc2JPEGOption, 155	fc2TIFFOption, 167
fc2JPG2Option, 156	fc2TimeStamp, 168
fc2MJPGOption, 159	fc2TriggerDelay, 170
iozivioi doption, 100	fc2TriggerDelayInfo, 173
ROIPosition	fc2TriggerMode, 174
fc2EmbeddedImageInfo, 135	fc2TriggerModeInfo, 176
-,	

rows	sourceMask
fc2Image, 151	fc2TriggerModeInfo, 176
	sourcePort
SYNC_ERROR_ALREADY_STARTED	fc2GigEStreamChannel, 149
MultiSyncLibraryDefs_C.h, 198	stride
SYNC_ERROR_ALREADY_STOPPED	fc2lmage, 151
MultiSyncLibraryDefs_C.h, 198	Strobe, 37
SYNC_ERROR_CONTEXT_NOT_INITIALIZED	fc2GetStrobe, 37
MultiSyncLibraryDefs_C.h, 198	
SYNC_ERROR_FAILED	fc2GetStrobeInfo, 37
MultiSyncLibraryDefs_C.h, 198	fc2SetStrobe, 38
SYNC_ERROR_OK	fc2SetStrobeBroadcast, 38
MultiSyncLibraryDefs C.h, 198	strobePattern
· · · · · · · · · · · · · · · · · · ·	fc2EmbeddedImageInfo, 135
SYNC_ERROR_UNKNOWN_ERROR	Structures, 115
MultiSyncLibraryDefs_C.h, 198	subnetMask
SYNC_MESSAGE_BUS_RESET	fc2CameraInfo, 127
MultiSyncLibraryDefs_C.h, 199	supported
SYNC_MESSAGE_DEVICE_ERROR	fc2LUTData, 158
MultiSyncLibraryDefs_C.h, 199	syncContext
SYNC_MESSAGE_FAILED	MultiSyncLibraryDefs_C.h, 198
MultiSyncLibraryDefs_C.h, 199	SyncCppImageToStruct
SYNC MESSAGE NOMASTER	FlyCapture2Internal_C.h, 193
MultiSyncLibraryDefs_C.h, 199	syncCreateContext
SYNC_MESSAGE_NOT_ENOUGH_DEVICES	MultiSyncLibrary C.h, 194
MultiSyncLibraryDefs_C.h, 199	· · · · ·
SYNC_MESSAGE_NOT_INITIALIZED	syncDestroyContext
MultiSyncLibraryDefs_C.h, 199	MultiSyncLibrary_C.h, 194
·	syncDisableCrossPCSynchronization
SYNC_MESSAGE_OK	MultiSyncLibrary_C.h, 195
MultiSyncLibraryDefs_C.h, 199	syncEnableCrossPCSynchronization
SYNC_MESSAGE_STARTED	MultiSyncLibrary_C.h, 195
MultiSyncLibraryDefs_C.h, 199	syncError
SYNC_MESSAGE_STOPPED	MultiSyncLibraryDefs_C.h, 198
MultiSyncLibraryDefs_C.h, 199	syncGetStatus
SYNC_MESSAGE_SYNCING	MultiSyncLibrary_C.h, 195
MultiSyncLibraryDefs_C.h, 199	syncGetTimeSinceSynced
SYNC_MESSAGE_THREAD_ERROR	MultiSyncLibrary_C.h, 195
MultiSyncLibraryDefs_C.h, 199	syncIsTimingBusConnected
SYNC MESSAGE UNKNOWN ERROR	MultiSyncLibrary_C.h, 196
MultiSyncLibraryDefs_C.h, 199	
screenHeight	syncMessage
fc2SystemInfo, 166	MultiSyncLibraryDefs_C.h, 198
screenWidth	syncQueryCrossPCSynchronizationSetting
fc2SystemInfo, 167	MultiSyncLibrary_C.h, 196
	syncRescanMasterTimingBus
seconds	MultiSyncLibrary_C.h, 196
fc2TimeStamp, 168	syncStart
sensorInfo	MultiSyncLibrary_C.h, 197
fc2CameraInfo, 126	syncStop
sensorResolution	MultiSyncLibrary_C.h, 197
fc2CameraInfo, 126	sysMemSize
serialNumber	fc2SystemInfo, 167
fc2CameraInfo, 126	,
shutter	TRUE
fc2EmbeddedImageInfo, 135	MultiSyncLibraryDefs_C.h, 198
softwareTriggerSupported	TypeDefs, 98
fc2TriggerModeInfo, 176	temperature
source	fc2CameraStats, 129
fc2StrobeControl, 163	timeSinceBusReset
fc2Strobelofito, 165	fc2CameraStats, 129
	timeSinceInitialization
fc2TriggerMode, 174	umeomcemualization

fc2CameraStats, 129	fc2CheckDriver, 93
timeStamp	fc2ErrorToDescription, 94
fc2CameraStats, 129	fc2GetDriverDeviceName, 94
timestamp	fc2GetLibraryVersion, 94
fc2EmbeddedImageInfo, 135	fc2GetSystemInfo, 94
TopologyNode Operation, 87	fc2LaunchBrowser, 96
fc2CreateTopologyNode, 88	fc2LaunchCommand, 96
fc2DestroyTopologyNode, 88	fc2LaunchCommandAsync, 96
fc2TopologyNodeAddChild, 88	fc2LaunchHelp, 97
fc2TopologyNodeAddPortType, 89	
fc2TopologyNodeAssignGuidToNode, 89	value
fc2TopologyNodeAssignGuidToNodeEx, 89	fc2GigEProperty, 148
fc2TopologyNodeGetChild, 90	fc2PGRGuid, 161
fc2TopologyNodeGetDeviceId, 90	valueReadable
fc2TopologyNodeGetGuid, 90	fc2TriggerModeInfo, 176
fc2TopologyNodeGetInterfaceType, 90	valueA
fc2TopologyNodeGetNodeType, 91	fc2TriggerDelay, 170
fc2TopologyNodeGetNumChildren, 91	valueB
fc2TopologyNodeGetNumPorts, 91	fc2TriggerDelay, 170
fc2TopologyNodeGetPortType, 92	vendorName
Trigger, 31	fc2CameraInfo, 127
fc2FireSoftwareTrigger, 31	vendorPixelFormatBitField
fc2FireSoftwareTriggerBroadcast, 32	fc2Format7Info, 142
fc2GetTriggerDelay, 32	fc2GigEImageSettingsInfo, 146
fc2GetTriggerDelayInfo, 32	vendorUniqueInfo_0
fc2GetTriggerMode, 33	fc2ConfigROM, 133
fc2GetTriggerModeInfo, 33	vendorUniqueInfo_1
fc2SetTriggerDelay, 34	fc2ConfigROM, 133
fc2SetTriggerDelayBroadcast, 34	vendorUniqueInfo_2
fc2SetTriggerMode, 35	fc2ConfigROM, 134
fc2SetTriggerModeBroadcast, 35	vendorUniqueInfo_3
type	fc2ConfigROM, 134
fc2TriggerDelay, 170	3 - , -
fc2TriggerDelayInfo, 173	whiteBalance
fc2Version, 177	fc2EmbeddedImageInfo, 135
TypeDefs, 98	width
BOOL, 98	fc2Format7ImageSettings, 139
	fc2GigEImageSettings, 145
FALSE, 98	fc2H264Option, 150
FULL_32BIT_VALUE, 98	,
fc2AVIContext, 98	xmlURL1
fc2Context, 98	fc2CameraInfo, 127
fc2GuiContext, 99	xmlURL2
fc2ImageImpl, 99	fc2CameraInfo, 127
fc2ImageStatisticsContext, 99	
fc2TopologyNodeContext, 99	
MAX_STRING_LENGTH, 98	
TRUE, 98	
unitBytesPerPacket	
fc2Format7PacketInfo, 143	
unitSWVer	
fc2ConfigROM, 133	
unitSpecId	
fc2ConfigROM, 133	
unitSubSWVer	
fc2ConfigROM, 133	
userDefinedName	
fc2CameraInfo, 127	
Utilities, 93	